ML 64847



50670010124104

USAARL Report No. 93-13

United States Army Aeromedical Research Laboratory

Fort Rucker, Alabama 36362-5292



RMSTRONG

User's Manual for BRNSIM/BURNSIM: A Burn Hazard Assessment Model

By

F. S. Knox, III Dena Bonetti Chris Perry

Escape and Impact Branch Biodynamics and Biocommunications Division

February 1993

20050901 031

Approved for public release; distribution unlimited.

ABORATORY

AIR FORCE SYSTEMS COMMAND WRIGHT-PATTERSON AIR FORCE BASE. OHIO 45433-6573

Notice

Qualified requesters

Qualified requesters may obtain copies from the Defense Technical Information Center (DTIC), Cameron Station, Alexandria, Virginia 22314. Orders will be expedited if placed through the librarian or other person designated to request documents from DTIC.

Change of address

Organizations receiving reports from the U.S. Army Aeromedical Research Laboratory on automatic mailing lists should confirm correct address when corresponding about laboratory reports.

Animal use

In conducting the research described in this report, the investigators adhered to the <u>Guide for Laboratory Animal Facilities and Care</u>, as promulgated by the Committee on the <u>Guide for Laboratory Animal Resources</u>, National Academy of Sciences-National Research Council.

Disposition

Destroy this document when it is no longer needed. Do not return it to the originator.

Disclaimer

The views, opinions, and/or findings contained in this report are those of the author(s) and should not be construed as an official Department of the Army position, policy, or decision, unless so designated by other official documentation. Citation of trade names in this report does not constitute an official Department of the Army endorsement or approval of the use of such commercial items.

Reviewed:

CHARLES A. SALTER

LTC, MC

Director, Biomedical Applications

arles a. Salter

Research Division

ROGER W WILEY, O. D., Ph.D.

Chairman, Scientific

Review Committee

Released for publication:

DAVID H. KARNEY

Colonel, MC, SFS

Commanding

REPORT DOCUMENTATION PAGE

Form Approved
OMB No. 0704-0188

Published participating burden for this collection of information is estimated to such as all nour per response, including the time for releasing instructions, searching existing data sources, gathering and maintaining the data needed, and completing and review in a toward existing of information. Send comments reparating this burden estimate or any other aspect of this collection of information in ordering suggestions for reducing this burden. It. A assentation Headquarters Services, Directorate for information Operations and Reports, 1215 Lefferson Davis Highway, Suite 1204. Arlington, VAI 22202-4302, and to the Office of Management and Budger, Paperwork Reduction Project (2704-0188), Washington, DC 20503.

1. AGENCY USE ONLY (Leave blank)	2. REPORT DATE	3. REPORT TYPE AN	D DATES COVERED
	1993 February	Interim - 19	80–1992
4 TITLE AND SUBTITLE			5. FUNDING NUMBERS
User's Manual for BRNSIM/F	BURNSIM: A Burn Haza	rd	PE - 62202A
Assessment Model			PR - 7231
	· · · · · · · · · · · · · · · · · · ·		TA - 723124
6. AUTHOR(S)			WU - 72312403
F.S. Knox III			
Dena Bonetti			
Chris Perry			ORGANIZATION
7. PERFORMING ORGANIZATION NAME		4 12 1	8. PERFORMING ORGANIZATION REPORT NUMBER
Crew Systems Directorate		y Aeromedical	
Armstrong Laboratory		h Laboratory	USAARL Report No. 93-13
Human Systems Center	Box 6205		00////// Neport 110: 33-13
Wright-Patterson AFB OH 4	5433-65/3 Fort Ruc	-0577	
9. SPONSORING / MONITORING AGENCY	NAME (S) AND ADDRESS (SS)	0377	10. SPONSORING / MONITORING
9. SPUNSORING / MUNITORING AGENCY	MANIE(S) AND ADDRESS(ES)		AGENCY REPORT NUMBER
U.S. Army Medical Research	th & Development Comm	and	·
Fort Detrick MD 27514-500	10		
	Defense Nucle	ar Agency	
Human Systems Center	RAAP		
Brooks AFB TX 78235-5000	Washington DC	f a program su	upported by both the U.S.
11. SUPPLEMENTARY NOTES This r Army Medical R&D Command	through its U.S. Ar	my Aeromedical	Research Laboratory at
Fort Rucker) and the U.S.	Air Force (Materiel	s Laboratory,	Life Support SPO, and
Armstrong Laboratory) fro	om 1970-1992. The se	nior author ha	is been the principal
investigator throughout. 12a DISTRIBUTION AVAILABILITY STAT	EMENT		12b. DISTRIBUTION CODE
TEG. DISTINGUISM: ATTICKED ATTICK			
Approved for public relea	ear distribution is	unlimited	
Approved for public felea	se, distribution is	unimiced	

13. ABSTRACT (Maximum 200 words)

BURNSIM is an interactive computer model which runs on DEC minicomputers (PDP 11 and VAX), Macintosh and IBM compatible PCs. The model is based on the work of Moritz and Henriques at Harvard, the Surgery Department at University of Rochester; Alice Stoll at Naval Air Development Center and Knox et al. at the U.S. Army Aeromedical Research Laboratory. Its development has been funded by the U.S. Army, U.S. Air Force, and Dr. Knox. The model predicts time to pain and burn depth when bare skin is exposed to any arbitrary time history of heat flux. It predicts burn depth with reasonable accuracy for pig and human skin. A software module to include clothing between the thermal source and the skin has been developed but not integrated with BURNSIM and has not been validated. By using sensors to measure heat flux behind fabric it has been possible to use BURNSIM to evaluate the insulating effect of clothing. BURNSIM has been used in the last several years to assess the burn hazard associated with rocket plumes in side-by-side ejection seats, shoulder launched weapons, nuclear flash and live fire. This manual provides information on model development, its installation and use on a PC.

14. SUBJECT TERMS Burns	15. NUMBER OF PAGES 70		
Computer model	Thermal protection Burn hazard predic	16. PRICE CODE	
17. SECURITY CLASSIFICATION OF REPORT	18. SECURITY CLASSIFICATION OF THIS PAGE	19. SECURITY CLASSIFICATION OF ABSTRACT	20. LIMITATION OF ABSTRACT
Unclassified	Unclassified	Unclassified	Unlimited

Acknowledgments

The senior author wishes to express his gratitude to the many colleaques who have contributed to the development of BURNSIM. Drs. Stanley C. Knapp, Thomas L. Wachtel, and Chap McCahan have worked on the project from the beginning in 1970 when we were all stationed at the U.S. Army Aeromedical Research Laboratory. Dr. Knapp had started the project to study postcrash fires with funding from various sources including the U.S. Army Medical Research and Development Command and the USAF Life Support Systems Program Office at Wright-Patterson Air Force Base. Dr. Cal Lum helped during the data collection phase in 1972. Dr. Daniel D. Reneau and his graduate student, Nelson O'Young, contributed the basic section of code to calculate the conductive heat transfer. Randy Nockton and Chet Ellis contributed additional software development including tape reading routines, statistical analysis programs and a database to manage the data. Dr. Charles Yuell, a pathologist at the Rochester School of Medicine, helped clarify the burn depth grading scheme and even found some of the original porcine skin samples from earlier burn studies at Rochester. Mr. Chris Perry and CPT Dena Bonetti have worked with BURNSIM for the past 3 years at the Armstrong Laboratory and have contributed to the current effort supported by the Defense Nuclear Agency. Part of this effort is the PC version of BURNSIM for which CPT Dena Bonetti is largely responsible. Funding for this effort has come from the U.S. Army Medical R&D Command, Defense Nuclear Agency, and the U.S. Air Force without which BURNSIM would not have been developed.

Table of contents

Background	ı.	•	•	•	•	•		•	•	•	•	•	•	•	•	•	•	•	•	•	•	•	٠	•	•	•	•	•	•	1
Model des	cri	pt.	io	n	•	•		•	•		•	•	•	•		•				•	•	•	•	•		•	•	•	٠	3
Getting	7 8	ta	rt	ed	•					•						•			•	•	•		•	•					•	3
Helpfu!	l h	in	ts					•			•					•	•	•	•				•				•		•	19
References			•	٠						•	•														•		•			21
Bibliograp																														
Appendix A																														
Appendix 1																														
Appendix (
								L	is	t	of	<u>i</u>	<u>11</u>	us	tr	at	<u>io</u>	ns												
Figure 1.						_			-	-																-				
Figure 2.				_																							•	•	•	4
Figure 3.	Sk	in	t	emj	pe	rai	tu	res	3 8	at	f	Lre	3t	8	Ĺχ	no	ođe	28	C	alo	cu l	lat	:ec	f						
		4 4	ъ.		~~		£.	~~	04	1	וו		а.	٠.																10

Background

BRNSIM (or BURNSIM as it is now called) is a computer model which allows the user to convert heat flux incident to bare skin to a predicted burn depth. The requirement for such a model arose when there was a need to quantify the thermal protective properties of new flight suits. Techniques employed in the 1960s and very early 1970s did not predict the full range of burns from no burn to full thickness and failed to take into account both initial conditions of the skin and its adaptive behavior when heated.

Since the late 1960s, the U.S. Army Aeromedical Research Laboratory (USAARL) at Fort Rucker, Alabama, has been involved in quantifying the burn hazard associated with post crash fires and the protective capability of flight clothing. USAARL staff (including the author) conducted a number of field studies using burning helicopters to establish the severity and time course of post crash fires (Knapp and Knox, 1982). They also 1) built and used two fire simulators to study the effect of simulated postcrash fires on pigs as an analog for man (Knox et al., 1978b), 2) placed fabrics between the fire and the pigs to study their protective capability (Knox et al., 1980), 3) assembled a large porcine (pig) burn database using this bioassay method (Knox, 1979a), and 4) developed the model, BRNSIM, to decrease the workload associated with using the bioassay method to assess fabric protective capabilities (Knox, 1979b).

The starting point for building BRNSIM (short for burn simulation) was the work of Alice Stoll who based her model on Moritz and Henriques' damage integral (Henriques, 1947). She had collected data from human volunteers on the time/heat flux relationships resulting in threshold transepidermal necrosis. This burn is represented by minor blister formation. To explain her results she added a consideration of damage occurring during cooling as well as during the heating phase (Figure 1). Stoll chose the constants (Stoll and Greene, 1959) in her model to fit her human data on threshold burns; more severe burns were not at first considered. Later Weaver and Stoll (1969) proposed an extension of Stoll's first model to include more severe burns without experimental basis.

The first model to come out of the USAARL program was that of Art Takata of IITRI (Takata, 1974) who worked for USAARL as a contractor. He started with Stoll's approach and added water boiling as a way of handling blister formation. He then adjusted the constants ($P,\Delta E$) (see equation (7) in Appendix A) to more accurately predict USAARL's data on more severe porcine burns.

¹The development of this model and the work upon which it is based has been funded by U.S. Army Medical Research & Development Command, Fort Detrick; U.S. Air Force Life Support Systems Program Office and Armstrong Laboratory, Wright-Patterson Air Force Base, Ohio; Defense Nuclear Agency, Washington D.C., and as a personal project by the primary author.




Figure 1. Tissue damage integral indicative of the blister endpoint (Stoll and Chianta, 1971)

The current BURNSIM model builds on these earlier efforts (Henriques, 1947; Weaver and Stoll, 1969; Mehta and Wong, 1973; Morse et al., 1973; and Takata, 1974). It is an interactive model written in both FORTRAN and ZBASIC and runs on PDP 11/40, 11/03, 11/24, VAX 11/780, Macintosh, and IBM compatible PCs.

Model description

BURNSIM considers the skin to be represented as 12 chunks or nodes (See Figure 2). Seven additional nodes can be inserted between the first and second nodes when exposures are mild and burn damage is likely to be shallow (Figure 2). BURNSIM solves the Fourier heat conduction equation to find temperature as a function of time at each node. Then total damage at each node is found by computing the damage integral at each depth. The transition between normal and damaged skin is defined as that depth where the damage integral is equal to one. For a more detailed description of the mathematics of BURNSIM consult Appendix A. BURNSIM source code (FORTRAN version) can be found in Appendix B.

Getting started

BURNSIM has been supplied to you in either source or compiled form. The following instructions are intended to help you use the model. The instructions and comments are based, in part, on feedback received from several users who have attempted to get started without the benefit of this manual. If you have problems using BURNSIM please do not hesitate to call the author at DSN 785-3931 or (513) 255-3931. Future versions of this manual will incorporate your comments and suggestions so that we may continue to improve BURNSIM and to distribute updated versions to the users.

The first step is to load the code for the model into your computer from the medium provided. This step has many versions. Only one example is given because it is assumed that if you are using this model you are sufficiently computer literate to load and compile the source code on your system.

PC Example: BURNSIM.FOR, REN12.DAT on floppy disk. To run off hard disk: Set default disk drive to a: Put diskette in a: Type DIR (rtn) BURNSIM.FOR REN12.DAT FLUX.DAT BURNSIM.EXE A>CD C: C>MD C:\BURNSIM C>CD C:\BURNSIM C>COPY a:*.* c: C:\BURNSIM>DIR FLUX.DAT BURNSIM. FOR REN12.DAT BURNSIM.EXE C:\BURNSIM>




Figure 2. Skin representation

At this point you have made a directory on your hard disk for BURNSIM and copied the files from the floppy to the new directory. The file REN12.DAT contains the initial values of all the variables which are changeable within BURNSIM. Some of these values such as the conductivity and heat capacity for each node can only be changed by creating a new REN12.DAT with an editor or word processing program (see Appendix C for the layout of REN12.DAT). The model expects a flat ASCII file, so if you use a word processor, save the file as an ASCII text file and not a document. Other values such as exposure time (ETIME) can be changed interactively as described below.

To run BURNSIM invoke the command for your system, e.g. RUN BURNSIM or BURNSIM. You will next see the following on the screen:

BURNSIM <CR>

The first screen that you see is shown below:

WELCOME TO BURNSIM. TO BEGIN RUNNING THE PROGRAM, BURNSIM FIRST NEEDS TO KNOW THE NAME OF THE FILE THAT YOU WANT TO STORE THE OUTPUT DATA IN. THIS FILE WILL CONTAIN ALL OF THE INPUT PARAMETERS AS WELL AS THE OUTPUT FOR EACH ITERATION THE MODEL PERFORMS. THIS FILE CAN BE CALLED ANYTHING UP TO EIGHT CHARACTERS LONG.

PLEASE ENTER A NAME FOR THE OUTPUT FILE: OUTFILE <CR>

The next screen is shown below:

NEXT BURNSIM WILL SHOW YOU THE PRESENT INPUT PARAMETERS.
UNDER THE LIST OF PARAMETERS YOU WILL SEE A QUESTION ASKING
IF YOU WISH TO CONTINUE. IF YOU WANT TO EXIT THE PROGRAM AT
THAT POINT, TYPE N. OTHERWISE TYPE Y.

TO CONTINUE ON TO THE LIST OF PARAMETERS TYPE A <CR>.

The following screen will appear:

SKIN DIFFUSION DATA INPUT PARAMETER LIST

TEMPIO =	32.5000	DENS =	1.00000	Q1 =	3.54000
BL =	.22000	AK =	.01000	JINC =	12
TEMPB =	4.5000	ABSORB =	.61300	BOIL =	100.15000
PL1 =	1.46000	PLN1 =	147.37000	DE1 =	50000.0
PL2 =	2.24000	PLN2 =	239.47000	DE2 =	80000.0
ETIME =	3.02000	ITIME =	80.00000	NXTRA =	= 0
BLOOD =	.00100				
APL1 =	.78000	APLN1 =	285.52000	ADE1 =	93534.9
APL2 =	.60000	APLN2 =	117.43000	ADE2 =	39109.8

DO YOU WISH TO CONTINUE? TYPE Y OR N Y <CR>

Answer yes (Y) to continue and you will be presented with the following choices:

TYPE THE NUMBER OF THE FUNCTION BELOW THAT YOU WISH TO PERFORM.

CHOOSE A FUNCTION NUMBER:

- 1 CHANGE SELECTED INITIAL VALUES
- 2 NO CHANGES--CONTINUE RUNNING THE PROGRAM
- 3 EXIT

PLEASE ENTER THE FUNCTION NUMBER: 1 <CR>

. Choose #1 to change the set up values. This will give you the following screen:

SKIN DIFFUSION DATA INPUT PARAMETER LIST

TEMPIO = 32.5000	DENS = 1.00000	Q1 = 3.54000
BL = .22000	AK = .01000	JINC = 12
TEMPB = 4.5000	ABSORB = .61300	BOIL = 100.15000
PL1 = 1.46000	PLN1 = 147.37000	DE1 = 50000.0
PL2 = 2.24000	PLN2 = 239.47000	DE2 = 80000.0
ETIME = 3.02000	ITIME = 80.00000	NXTRA = 7
BLOOD = .00100		
APL1 = .78000	APLN1 = 285.52000	ADE1 = 93534.9
APL2 = .60000	APLN2 = 117.43000	ADE2 = 39109.8

DO YOU WANT TO MAKE ANY CHANGES? Y OR N Y

Answer yes (Y) here to change the input values using the following screen:

PICK A NUMBER

1=TEMPIO	8=ETIME
2=DENS	9=PL1
3=Q1	10=PLN1
4=BL	11=PL2
5=AK	12=PLN2
6=JINC	13=DE1
7=TEMPB	14=DE2

15=ITIME 16=ABSORBTIVITY

17=BOIL 18=EXTRA NODES

19=BLOOD 20=APL1

21=APLN1 22=APL2

Choose the number representing the parameter you wish to change. The definition of these parameters is in Table I. For example, set up one of Stoll's published cases (Weaver and Stoll, 1969). In this case, the human skin was exposed for 5.6 seconds at 0.4 cal/cm²-sec. The skin was blackened with India ink to set the absorbtivity at 94 percent. Start by choosing #3 to set the incident flux level, Q1. The model responds with:

ENTER THE FLUX FILE NAME (TYPE A <CR> IF NO FILE IS TO BE USED): <CR>

Since Stoll's case has a constant flux value, type a (CR) and the following will appear on the screen:

CONSTANT Q-VALUE = 3.5400000 INPUT NEW VALUE: 0.4 <CR>

The old value was 3.54000 and the new value entered was 0.4 cal/cm²-sec.

If you do later simulations where you wish to read in a file of varying flux values instead of using a constant flux value, type the name of the flux file in response to the following statement:

ENTER THE FLUX FILE NAME (TYPE A <CR> IF NO FILE IS TO BE USED): FLUX.DAT

The file FLUX.DAT is the example flux file given on the disk. When creating flux files to be read into BURNSIM, remember that the file name can be no more than eight characters in length including the .DAT ending. Also the file must contain only one column of data, the flux data, in units of cal/cm²-sec. The number of points in the flux file and the sample interval between points must be known, too.

Continue to input responses to the following statements concerning the flux file as they appear on the screen:

ENTER FLUX ID (UP TO 8 CHARACTERS): IDFLUX (CR)

The FLUX ID can be any combination of 8 characters.

ENTER THE NUMBER OF POINTS IN THE FLUX PROFILE: 100 (CR)

The maximum number of points that can be read in is 600.

ENTER THE SAMPLE INTERVAL IN SECONDS: 0.1 (CR)

*** Note: When using a flux file for the incident flux, the exposure time (ETIME) variable must be set equal to the number of points in the flux file minus one times the sample interval in seconds. For this example, ETIME = (100 - 1) x (0.1) = 9.9 seconds.

The next screen is shown below:

SKIN DIFFUSION DATA INPUT PARAMETER LIST

TEMPIO = 32.5000 BL = .22000	DENS = 1.00000 AK = .01000	Q1 = .40000 JINC = 12
TEMPB = 4.5000	ABSORB = .61300	BOIL = 100.15000
PL1 = 1.46000	PLN1 = 147.37000	DE1 = 50000.0
PL2 = 2.24000	PLN2 = 239.47000	DE2 = 80000.0
ETIME = 3.02000	ITIME = 80.00000	NXTRA = 7
BLOOD = .00100		
APL1 = .78000	APLN1 = 285.52000	ADE1 = 93534.9
APL2 = .60000	APLN2 = 117.43000	ADE2 = 39109.8

DO YOU WANT TO MAKE ANY CHANGES? Y OR N Y

Answer yes (Y) here to change the next input value using the following screen:

PICK A NUMBER

1=TEMPIO	8=ETIME
2=DENS	9=PL1
3=Q1	10=PLN1
4=BL	11=PL2
5=AK	12=PLN2
6=JINC	13=DE1
7=TEMPB	14=DE2
15=ITIME	16=ABSORBTIVITY
17=BOIL	18=EXTRA NODES
19=BLOOD	20=APL1
21=APLN1	22=APL2

23=APLN2 24=ADE1 25=ADE2

18 <CR>

THE NUMBER OF EXTRA NODES IS: 0 INPUT NEW VALUE: 7 <CR>

ENTER NEW VALUES SEPARATED BY A COMMAS, OR A <CR>
IF THE PROGRAM IS TO CALCULATE VALUES. 25.,50.,75.,100.,125.,150.,175.

The next screen is shown below:

SKIN DIFFUSION DATA INPUT PARAMETER LIST

TEMPIO = 32.5000 BL = .22000	DENS = 1.00000 AK = .01000	Q1 = .40000 JINC = 12
TEMPB = 4.5000	ABSORB = .61300	BOIL = 100.15000
PL1 = 1.46000	PLN1 = 147.37000	DE1 = 50000.0
PL2 = 2.24000	PLN2 = 239.47000	DE2 = 80000.0
ETIME = 3.02000	ITIME = 80.00000	NXTRA = 7
BLOOD = .00100		
APL1 = .78000	APLN1 = 285.52000	ADE1 = 93534.9
APL2 = .60000	APLN2 = 117.43000	ADE2 = 39109.8

THE EXTRA NODES ARE: 25.0 50.0 75.0 100.0 125.0 150.0 175.0

DO YOU WANT TO MAKE ANY CHANGES? Y OR N Y

Answer yes (Y) here to change the next input value using the following screen:

PICK A NUMBER

1=TEMPIO	8=ETIME
2=DENS	9=PL1
3=Q1	10=PLN1
4=BL	11=PL2
5=AK	12=PLN2
6=JINC	13=DE1
7=TEMPB	14=DE2
15=ITIME	16=ABSORBTIVITY
17=BOIL	18=EXTRA NODES
19=BLOOD	20=APL1
21=APLN1	22=APL2

19 <CR>

THE VALUE FOR BLOOD IS: .00100 INPUT NEW VALUE: 0.0007 <CR>

The next screen is shown below:

SKIN DIFFUSION DATA INPUT PARAMETER LIST

TEMPIO = 32.5000 BL = .22000	DENS = 1.00000 AK = .01000	Q1 = .40000 JINC = 12
TEMPB = 4.50000	ABSORB = .61300	BOIL = 100.15000
PL1 = 1.46000	PLN1 = 147.37000	DE1 = 50000.0
PL2 = 2.24000	PLN2 = 239.47000	DE2 = 80000.0
ETIME = 3.02000 BLOOD = .00070	ITIME = 80.00000	NXTRA = 7
APL1 = .78000	APLN1 = 285.52000	ADE1 = 93534.9
APL2 = .60000	APLN2 = 117.43000	ADE2 = 39109.8

THE EXTRA NODES ARE: 25.0 50.0 75.0 100.0 125.0 150.0 175.0

DO YOU WANT TO MAKE ANY CHANGES? Y OR N Y

Answer yes (Y) here to change the next input value using the following screen:

PICK A NUMBER

1=TEMPIO	8=ETIME	
2=DENS	9=PL1	
3=Q1	10=PLN1	
4=BL	11=PL2	
5=AK	12=PLN2	
6=JINC	13=DE1	
7=TEMPB	14=DE2	
15=ITIME	16=ABSORBTIVITY	
17=BOIL	18=EXTRA NODES	
19=BLOOD	20=APL1	
21=APLN1	22=APL2	
23=APLN2	24=ADE1	25=ADE2

8 <CR>

THE VALUE FOR ETIME IS: 3.02000 INPUT NEW VALUE: 5.6 <CR>

The next screen is shown below:

SKIN DIFFUSION DATA INPUT PARAMETER LIST

TEMPIO = 32.5000 BL = .22000	DENS = 1.00000 AK = .01000	Q1 = .40000 JINC = 12
TEMPB = 4.50000	ABSORB = .61300	BOIL = 100.15000
PL1 = 1.46000	PLN1 = 147.37000	DE1 = 50000.0
PL2 = 2.24000	PLN2 = 239.47000	DE2 = 80000.0
ETIME = 5.60000	ITIME = 80.00000	NXTRA = 7
BLOOD = .00070		
APL1 = .78000	APLN1 = 285.52000	ADE1 = 93534.9
APL2 = .60000	APLN2 = 117.43000	ADE2 = 39109.8

THE EXTRA NODES ARE: 25.0 50.0 75.0 100.0 125.0 150.0 175.0

DO YOU WANT TO MAKE ANY CHANGES? Y OR N Y

Answer yes (Y) here to change the next input value using the following screen:

PICK A NUMBER

1=TEMPIO	8=ETIME	
2=DENS	9=PL1	
3=Q1	10=PLN1	
4=BL	11=PL2	
5=AK	12=PLN2	
6=JINC	13=DE1	
7=TEMPB	14=DE2	
15=ITIME	16=ABSORBTIVITY	
17=BOIL	18=EXTRA NODES	
19=BLOOD	20=APL1	
21=APLN1	22=APL2	
23=APLN2	24=ADE1	25=ADE2

16 <CR>

THE VALUE FOR ABSORB IS: 0.61300 INPUT NEW VALUE: 0.94 <CR>

The next screen is shown below:

SKIN DIFFUSION DATA INPUT PARAMETER LIST

TEMPIO = 32.5000	DENS = 1.00000	Q1 = .40000
BL = .22000	AK = .01000	JINC = 12
TEMPB = 4.50000	ABSORB = .94000	BOIL = 100.15000
PL1 = 1.46000 PL2 = 2.24000 ETIME = 5.60000 BLOOD = .00070	PLN1 = 147.37000 PLN2 = 239.47000 ITIME = 80.00000	DE1 = 50000.0 DE2 = 80000.0 NXTRA = 7
APL1 = .78000	APLN1 = 285.52000	ADE1 = 93534.9
APL2 = .60000	APLN2 = 117.43000	ADE2 = 39109.8

THE EXTRA NODES ARE: 25.0 50.0 75.0 100.0 125.0 150.0 175.0

DO YOU WANT TO MAKE ANY CHANGES? Y OR N N

At this point all of the input values for Stoll's example case have been set, so the answer here is no (N).

NOTE: If you inadvertently answer yes (Y) to make changes, and then decide not to make any, type a <CR> to exit the "PICK A NUMBER" menu, and the following question will appear:

DO YOU WISH TO CONTINUE? TYPE Y OR N Y <CR>

Type yes (Y) to continue on with the present run.

Now that the correct parameters are set up, select #2 to proceed:

TYPE THE NUMBER OF THE FUNCTION BELOW THAT YOU WISH TO PERFORM.

CHOOSE A FUNCTION NUMBER:

- 1 CHANGE SELECTED INITIAL VALUES
- 2 NO CHANGES--CONTINUE RUNNING THE PROGRAM
- 3 EXIT

PLEASE ENTER THE FUNCTION NUMBER: 2 <CR>

You are now ready to run the program. BURNSIM will ask you for some file names in which to store the data and summaries.

ENTER THE MODEL NAME OR DESCRIPTION (UP TO 80 CHARACTERS). THIS INFORMATION WILL BE USED AS A TITLE ON THE SUMMARY PAGE.

TEST OF A. STOLL'S .4CAL 5.6 SEC CASE FOR USER'S MANUAL <CR>

The following screen appears:

NOW ENTER THE SUMMARY FILENAME (UP TO 8 CHARACTERS). THIS FILE WILL CONTAIN A SUMMARY OF THE SIMULATION. SUM1 (CR)

Any name up to 8 characters can be used.

The next screen then appears:

NOW ENTER THE TEMPERATURE FILE (UP TO 8 CHARACTERS).
THIS FILE WILL CONTAIN A LIST OF THE TEMPERATURES
AT THE VARIOUS NODES DURING THE SIMULATION. TFILE1 (CR)

Any name up to 8 characters can be used.

While calculating, the model prints the following on the screen:

T=	XTIME=	TIME=	0.000000
32.50	0.0000E+00		
32.91	0.0000E+00		•
33.32	0.0000E+00		
33.73	0.0000E+00		
34.14	0.0000E+00		
34.55	0.0000E+00		
34.95	0.0000E+00		
35.36	0.0000E+00		
35.77	0.0000E+00		
36.18	0.0000E+00		
36.59	0.0000E+00		
37.00	0.0000E+00		
BLUD =.0000	00		

T =	XTIME=		TIME=	0.010000
32.96	0.0000E+00			
32.92	0.0000E+00			
33.32	0.0000E+00			
33.73	0.0000E+00			
34.14	0.0000E+00			
34.54	0.0000E+00			
34.95	0.0000E+00			
35.36	0.0000E+00			
35.77	0.0000E+00	•		
36.18	0.0000E+00			
36.59	0.0000E+00		4	
36.99	0.0000E+00			
BLUD =.0000	0			

```
T=
            XTIME=
                                                 TIME=
                                                        1.000000
    44.40
               0.0000E+00
   40.02
               0.0000E+00
   37.25
               0.0000E+00
   35.71
               0.0000E+00
   35.03
               0.0000E+00
   34.89
               0.0000E+00
    35.04
               0.0000E+00
               0.0000E+00
   35.33
               0.0000E+00
   35.67
   36.01
               0.0000E+00
   36.32
               0.0000E+00
   36.64
               0.0000E+00
BLUD = .00003
  T=
            XTIME=
                                                TIME= 2.000000
   49.19
               0.0000E+00
   44.62
               0.0000E+00
   41.24
               0.0000E+00
   38.86
               0.000E+00
   37.29
               0.0000E+00
   36.36
               0.0000E+00
   35.90
               0.0000E+00
   35.76
               0.0000E+00
   35.83
               0.0000E+00
   36.02
               0.0000E+00
   36.27
               0.0000E+00
   36.60
               0.0000E+00
BLUD = .00007
. part of the sequence omitted to save space.
  T=
            XTIME=
                                                TIME= 13.00000
   44.50
               0.0000E+00
   44.44
               0.0000E+00
   44.32
               0.0000E+00
   44.13
               0.0000E+00
   43.81
               0.0000E+00
   43.37
               0.0000E+00
   42.81
               0.0000E+00
   42.13
               0.0000E+00
   41.36
               0.0000E+00
   40.50
               0.0000E+00
   39.59
               0.0000E+00
   38.43
               0.0000E+00
BLUD = .00045
  T =
           XTIME=
                                                TIME= 14.000000
   44.02
              0.0000E+00
   43.97
              0.0000E+00
   43.86
              0.0000E+00
```

43.70	0.0000E+00
43.43	0.0000E+00
43.03	0.0000E+00
42.52	0.0000E+00
41.90	0.0000E+00
41.17	0.0000E+00
40.36	0.0000E+00
39.49	0.0000E+00
38.38	0.0000E+00
BI.UD = .00049	

$\mathbf{T}=$	XTIME=
44.00	0.0000E+00
43.95	0.0000E+00
43.85	0.0000E+00
43.69	0.0000E+00
43.41	0.0000E+00
43.02	0.0000E+00
42.51	0.0000E+00
41.89	0.0000E+00
41.17	0.0000E+00
40.36	0.0000E+00
39.48	0.0000E+00
38.38	0.0000E+00
BLUD = .0004	19

TIME= 14.040000

At the conclusion of the calculations, the following information appears on the screen:

W=1 LIES ABOVE NODE 2. INTERCOLLATING VALUES OF D AND W COMPUTED FROM INTERPOLATED VALUES OF D AND TEMPERATURE.

MAXIMUM TEMPERATURE = 60.056

THRESHOLD DEPTH = 104.6

FINAL TIME = 14.04

TIME TO PAIN = 1.59

TYPE A <CR> TO CONTINUE. <CR>

The next screen asks if you want to reformat the file so that it can be brought into the HARVARD GRAPHICS shell to make a plot.

DO YOU WANT TO PLOT THE TEMPERATURE VS. TIME IN HARVARD GRAPHICS? Y OR N Y \langle CR \rangle

If you answer yes (Y) then you must type in a new file name for the HARVARD GRAPHICS temperature file.

THE TEMPERATURE DATA IS STORED IN FILE: TFILE1

ENTER THE FILE TO STORE THE HARVARD GRAPHICS TEMPERATURES USING UP TO 12 CHARACTERS INCLUDING THE ENDING .DAT HGTFILE1.DAT

The following will then appear on the next screen:

THE MODEL OUTPUT IS IN FILE: OUTFILE
USE "PRINT" OR "TYPE " AFTER YOU EXIT THE PROGRAM TO SEE IT.

THE TEMPERATURES AT EACH NODE ARE IN FILE: TFILE1
USE "PRINT" OR "TYPE " AFTER YOU EXIT THE PROGRAM TO SEE IT.

THE TEMPERATURES FOR THE HARVARD GRAPHICS PLOTS ARE IN FILE: HGTFILE1.DAT USE "PRINT" OR "TYPE" AFTER YOU EXIT THE PROGRAM TO SEE IT.

THE SUMMARY PRINTOUT IS IN FILE: SUM1
USE "PRINT" OR "TYPE " AFTER YOU EXIT THE PROGRAM TO SEE IT.

TYPE A <CR> TO CONTINUE. <CR>

The following question will appear next on the screen:

DO YOU WANT TO CONTINUE? Y OR N

At this point choosing yes (Y) takes you back to the following screen:

TYPE THE NUMBER OF THE FUNCTION BELOW THAT YOU WISH TO PERFORM.

CHOOSE A FUNCTION NUMBER:

- 1 CHANGE SELECTED INITIAL VALUES
- 2 NO CHANGES--CONTINUE RUNNING THE PROGRAM
- 3 EXIT

PLEASE ENTER THE FUNCTION NUMBER:

If you choose no (N) at the "DO YOU WANT TO CONTINUE?" you will see the following question:

DO YOU WANT TO DO ANOTHER RUN? Y OR N

If you answer yes (Y) you will be taken back to the following screen to change any desired input parameters:

SKIN DIFFUSION DATA INPUT PARAMETER LIST

TEMPIO = 32.5000	DENS = 1.00000	Q1 = .40000
BL = .22000	AK = .01000	JINC = 12
TEMPB = 4.50000	ABSORB = .94000	BOIL = 100.15000
PL1 = 1.46000 PL2 = 2.24000 ETIME = 5.60000 BLOOD = .00070	PLN1 = 147.37000 PLN2 = 239.47000 ITIME = 80.00000	DE1 = 50000.0 DE2 = 80000.0 NXTRA = 7
APL1 = .78000	APLN1 = 285.52000	ADE1 = 93534.9
APL2 = .60000	APLN2 = 117.43000	ADE2 = 39109.8

THE EXTRA NODES ARE: 25.0 50.0 75.0 100.0 125.0 150.0 175.0

DO YOU WANT TO MAKE ANY CHANGES? Y OR N

If you answer no (N) to "DO YOU WANT TO DO ANOTHER RUN?", you will exit the BURNSIM program.

If you type the file SUM1 the following appears on the screen:

MODEL NAME OR DESCRIPTION: TEST OF A. STOLL .4CAL 5.6SEC CASE

SKIN DIFFUSION DATA INPUT PARAMETER LIST

TEMPIO = BL =	32.50000 .22000	DENS = 1.00000 AK = .01000	Q1 = .40000 JINC = 12
TEMPB =	4.50000	ABSORB = .94000	BOIL = 100.15000
PL1 =	1.46000	PLN1 = 147.37000	DE1 = 50000.0
PL2 =	2.24000	PLN2 = 239.47000	DE2 = 80000.0
ETIME = BLOOD =	5.60000	ITIME = 80.00000	NXTRA = 7
APL1 =	.78000	APLN1 = 285.52000	ADE1 = 93534.9
APL2 =	.60000	APLN2 = 117.43000	ADE2 = 39109.8

THE EXTRA NODES ARE: 25.0 50.0 75.0 100.0 125.0 150.0 175.0

FLUX FILE I.D.: .00 2

FLUX(I) =
1 .400 2 .400

W= .21973E+01
W= .12061E+00
W= .14088E-01

D= -.16000E+02

```
D= .52983E+01
D= .59915E+01
```

W=1 LIES ABOVE NODE 2. INTERCOLLATING VALUES OF D AND W COMPUTED FROM INTERPOLATED VALUES OF D AND TEMPERATURE.

W=	.10360E+01			
W=	.86923E+00			
W=	.73320E+00			
				•
D=	.46052E+01			
D=	.48283E+01			
D=	.50106E+01			
W =	.21973E+01 A	T DEPTH	(IN MICRONS)=	.112535E-06
W =	.18217E+01 A	T DEPTH	(IN MICRONS)=	25.0000
W =	.14992E+01 A	T DEPTH	(IN MICRONS)=	50.0000
W =	.12423E+01 A	T DEPTH	(IN MICRONS)=	75.0000
W =	.10360E+01 A	T DEPTH	(IN MICRONS)=	100.000
W =	.86923E+00 A	T DEPTH	(IN MICRONS)=	125.000
W =	.73320E+00 A	T DEPTH	(IN MICRONS)=	150.000
W =	.62140E+00 A	T DEPTH	(IN MICRONS) =	175.000
W =	.12061E+00 A	T DEPTH	(IN MICRONS)=	200.000
W =	.14088E-01 A	T DEPTH	(IN MICRONS)=	400.000
W =	.47704E-02 A	T DEPTH	(IN MICRONS) =	600.000
W =	.21844E-02 A	r depth	(IN MICRONS) =	800.000

MAXIMUM TEMPERATURE = 60.056

THRESHOLD DEPTH = 104.6

FINAL TIME = 14.04

TIME TO PAIN IS 1.59 SECONDS.

If you plot the data saved in TFILE1 and overlay Stoll's measured data, we get the following:




Figure 3. Skin temperatures at first six nodes calculated with Burnsim for Stoll's Data

Notice that there is reasonable fit between the computed temperature profiles and the recorded temperature. The predicted depth is 104.9 microns. Stoll observed a threshold blister, hence the damage should be between $80\mu m$ and $120\mu m$.

Helpful hints

This section is devoted to explaining the inputs to the model and some hints about how to set up the model for special cases. The inputs are summarized in Table A-1.

There are nine special cases which have been found by previous users. First, for short exposures of less than 1 second, change the calculation interval (AK) from its normal value of .01 second to some value which is at least 100 times less than the duration. Thus, for an

exposure of 0.1 sec use AK = 0.001 second. Second, if the skin has been blackened, e.g., with india ink, use an absorptivity of about 0.92 to 0.94. Third, the default value of 0.613 for absorptivity assumes that 100 percent of the convective energy is absorbed, only 60 percent of the radiative energy is absorbed, and 5 percent of incident radiation is intercepted by hair. Thus, assuming

- 1) Q incident = 0.1 qi (convective) + 0.9 qi (radiative)
- 2) 5 percent radiative is not absorbed because of hair stubble,

then Q = 0.1 qi + 0.6(.9)(.95)qi = 0.613 qi

Fourth, use NXTRA 7 especially for mild exposures so that shallow burn depths are calculated more accurately. Fifth, a value of 0.0007 for Blood works best for shallow human burns.

Sixth, new values for DE1, DE2, PL1, PLN1, PL2, and PLN2 can be calculated if you wish to try rate constants published by other authors (see model derivation in Appendix A).

Seventh, it is possible to calculate new thermal properties based on humidity changes. Read the paper on thermal properties published in the journal Burns (Knox et al. 1986).

Eighth, the model currently assumes that ambient temperature is 23.9°C. Thus, during cool down the surface loses heat to a 23.9°C environment. This number can be changed only in the source code in the following line:

If (TIME.GE.ETIME)Q1 = -5.E-4*(t(1)-23.9)

Nine, for very severe exposures, where water boils in more than the first node, the thermal property recalculations routine causes an instability in the cool down phase. This can be seen if the data are plotted and can be avoided by setting the boil temperature to a much higher value. A permanent fix for this bug will appear in the next version of BURNSIM.

References

- Crank, J., and Nicholson, P. 1947. <u>Proceedings Cambridge philoslogical</u> society. 43:50
- Henriques, F. C. 1947. Studies of thermal injury. V. The predictability and the significance of thermally induced rate processes leading to irreversible epidermal injury. <u>Archives of pathology</u>. 43:489-502.
- Knapp, S. C., and Knox, Francis, S. III. 1982. Human response to fire and personnel protection measures. AGARD/NATO Pep lecture series no. 123 on "Aircraft Fire Safety", 7-16 June, at Oslo, Norway, London, England and Washington, D.C.
- Knox, F. S., III, Wachtel, T. L., and Knapp, S. C. 1978a. How to measure the burn-preventive capability of nonflammable textiles: A comparison of the USAARL porcine bioassay technique with mathematical models. <u>Burns</u>. 5(1):19-29. Also reprinted as USAARL Report No. 79-5. 1979. (Uses model and sensor output to predict burns.)
- Knox, F. S., III, Wachtel, T. L., and Knapp, S. C. 1978b. Biomedical constraints on thermal protective flight clothing design: A bioengineering analysis. In <u>Operational helicopter aviation medicine</u>: AGARD/NATO Panel Specialists' Meeting, May 1-5; Fort Rucker, AL. London: Technical Editing and Reproduction Ltd. pp. 63-1--63-11. AGARD-CP-255.
- Knox, F. S., III, Wachtel, T. L., and Knapp, S. C. 1978c. Mathematical models of skin burns induced by simulated postcrash fires as aids in ther- mal protective clothing design and selection. In Proceedings of the army science conference, June 20-22; West Point, NY, 267-281. Vol II (AD-A056437). Also published as USAARL Report No. 78-15.
- Knox, F. S., III, Knapp, S. C., McCahan, G. R., Jr., and Wachtel, T. L. 1979. Bioassay of thermal protection afforded by candidate flight suit fabrics. <u>Journal of aviation</u>, <u>space</u>, <u>and environmental</u> <u>medicine</u>. 50(10):1023-1030.
- Knox, F. S., III. 1979. <u>Predictability of burn depth: Data analysis and mathematical modeling based on USAARL's experimental porcine burn data</u>. Shreveport, LA: Louisiana State University School of Medicine, Department of Physiology and Biophysics. Contract DAMD17-77-7004.
- Knox, F. S., III, Wachtel, T. L., and Knapp, S. C. 1980. Burn prediction model for thermally protective clothing evaluation. Paper presented at the annual meeting of the Aerospace Medical Association, 12-15 May.

- Knox, F. S., III, Wachtel, T. L., McCahan, G. R., Jr., and Knapp, S. C. 1986. Thermal properties calculated from measured water content as a function of depth in porcine skin. <u>Burns</u>. 12(8):556-562.
- Mehta, A., and Wong, F. 1973. <u>Measurement of flammability and burn potential of fabrics</u>. (Summary report December 1971-January 1973.) Cambridge, MA: Fuels Research Laboratory, Massachusetts Institute of Technology Project DSR 73884.
- Moritz, A. R. 1947. Studies of thermal injury. III. The pathology and pathogenesis of cutaneous burns, an experimental study. American journal of pathology. 23:915-941.
- Morse, H. L., Thompson, J. G., Clark, K. J., Green, K. A., and
 Moyer, C. B. 1973. Analysis of the thermal responses of
 protective fabrics. Wright-Patterson Air Force Base, OH: Air
 Force Materials Laboratory, Air Force Systems Command. Technical
 Report AFML-TR-73-17.
- Reneau, D. D., and O'Young, Nelson. 1976, 1977, 1978. Consultation report to F. S. Knox. Shreveport, LA: Louisiana State University Medical Center, Department of Physiology and Biophysics. U.S. Army Contract Nos. DABT01-75-C-0257 and DAMD-17-77-C-7004.
- Rushmer, R. F., Buettner, K. J. K., Short, J. M., and Odland, G. F. 1966. The skin. <u>Science</u>. 154(3747):343-348.
- Stoll, A., and Greene, L. C. 1959. Relationship between pain and tissue damage due to thermal radiation. <u>Journal of applied physiology</u>. 14:373.
- Stoll, A. M., and Chianta, M. A. 1971. Heat transfer through fabrics as related to thermal injury. Transactions-New York academy of science. Vol 33(7):649-670. November.
- Takata, A. 1974. Development of criterion for skin burns. <u>Aerospace</u> medicine. 45(6):634-637.
- Weaver, J. A., and Stoll, A. M. 1969. Mathematical model of skin exposed to thermal radiation. <u>Aerospace medicine</u>. 40:24-30.

Bibliography

- Albright, J. D., Knox, F. S. III, DuBois, D. R., and Keiser, G. M. 1971a.

 The testing of thermal protective clothingin a reproducible fuel fire environment, phase I report: a feasibility study. Fort Rucker, AL:

 U.S. Army Aeromedical Research Laboratory. USAARL LR 71-3-3-2.
- Albright, J. D., Knox, F. S. III, DuBois, D. R., and Keiser, G. M. 1971b.

 The testing of thermal protective clothing in a reproducible fuel fire environment, a feasibility study. Fort Rucker, AL: U.S. Army Aeromedical Research Laboratory. USAARL Report No. 71-24. (Defines postcrash fire environment and assesses the proper directions of future research.)
- Anderson, W. A. D. 1966. <u>Pathology</u>. 5th ed., Vol. 1. St. Louis, MO: The C.V. Mosby Company.
- Archanbeau, J. O., Fairchild, R. G., and Commerford, S. L. 1966. Response of skin of swine to increasing exposure of 250-KVP X-ray. In: Bustad, L.K. and McClellan, R.O., ed. <u>Swine in biomedical research</u>. Seattle: Frayn. 463.
- Armed Forces Institute of Pathology. <u>AFIP manual of histologic and special staining technique</u>. 2d ed. New York: Blackstone Division of McGraw Hill Book Company.
- Artz, C. P., and Moncrief, J. A. 1969. <u>The treatment of burns</u>. 2d ed. Philadelphia, PA: W.B. Saunders Company.
- Bader, B. E. 1965. <u>Heat transfer in liquid hydrocarbon fuel fires</u>. In: Chemical Engineering Progress Symposium Series. pp. 78-90. Vol. 61, No. 56. Sandia Albequerque, NM.
- Basar, Erol. 1976. The circulatory autoregulation. In: <u>Biophysical and physiological systems analysis</u>. Reading, MA: Addison-Wesley Publishing Company. Chapter 4.
- Berkley, K. M. 1954. <u>Evaluation of surface appearance of burns by depth of damage</u>. Rochester, NY: University of Rochester. Atomic Energy Report UR-337.
- Berkley, K. M., Pearse, H. E., and Davis, T. P. 1954. Studies of flash burns: the influence of skin temperature in the production of cutaneous burns in swine. Rochester, NY: University of Rochester. Atomic Energy Project UR-338.
- Berkley, K. M. 1957. The effect of air space on sub-fabric burns in swine. Rochester, NY: The University of Rochester. Atomic Energy Project UR-490.
- Billote, J. B., Coumans, R. J. K., Guthy, E. A., Constable, J. D., and Burke, J. F. 1969. Effect of topical sulfamylon on wound healing. <u>Surgical forum</u>. 20:71.
- Blinov, V. I., and Khuiakov, G. N. 1957. Certain laws governing the diffusive burning of liquids. <u>Academic Nauk, SSSR Doklady</u>. 113:1094-1098. (Reviewed by H.C. Hottel, 1959, <u>Fire research abstracts and reviews 1</u>, pp 41-44.)

- Bruce, G. H., Peaceman, D. W., Rackford, H. H., and Rice, J. D. 1953.

 <u>Transactions American institute of mining, metallurgical and petroleum engineers</u>. 198:79.
- Buettner, K. 1952. Effects of extreme heat and cold on human skin. III.

 Numerical analysis and pilot experiments on penetrating flash radiation effects. <u>Journal of applied physiology</u>. 5(5):207-220.
- Burgess, D. S., Grumer, J., and Wolfhard, H. G. 1961. Burning rates of liquid fuels in large and small open trays. In: Berl, W. G., ed. <u>The use of models in fire research</u>. Publication. 786. Washington, DC:
 National Academy of Sciences National Research Council. 68-75.
- Bustad, L. K; 1966, Pigs in the laboratory. Scientific American. 214:94.
- Bustad, L. K., and McClellan, R. O., ed. 1966. <u>Swine in biomedical research</u>. Seattle, WA: Frayn.
- Butterfield, W. S. H., and Dixey, J. R. B. 1951. Burns from atomic bombs, Journal royal naval medical science. 37:9.
- Callen, H. B. 1960. Thermodynamics. New York, NY: John Wiley & Sons, Inc.
- Carhart, W. H., and Affens, W. A. 1969. Flammability of aircraft fuels. Fire technology. 5(1):16.
- Carslaw, H. S., and Jaeger, J. C. 1959. <u>Conduction of heat in solids</u>. Oxford, Oxford Press University. QC 321.C28
- Conley, D. W. 1965. <u>Post-crash fire-fighting studies on transport category</u>
 <u>aircraft</u>. Atlantic City, NJ: Federal Aviation Agency. Report RD-65-50.
- Crank, J., and Nicholson, P. 1947. <u>Proceedings Cambridge philoslogical</u> society. 43:50.
- Dalzell, W. H., and Sarofim, A. F. 1969. Optical constants of soot and their application to heat-flux calculations. <u>Journal of heat transfer transactions of the American society of mechanical engineers</u>. 100-104.
- Derksen, W. L., Delhevy, G. P., and Monahan, T. I. 1960. <u>Thermal and optical properties of the NML skin stimulant</u>. New York, NY: Naval Materials Laboratory, New York Naval Shipyard. Laboratory Project 5046-3.
- Diller, K. R. 1985. Analysis of skin burns. In Shitzer A., Eberhart, R. C. eds: <u>Heat transfer in medicine and biology: Analysis and applications, Vol 2</u>. New York: Plenum Publishing Co. 85-134.
- Dumphy, J. E. 1966. Whither repair? In: Levenson, S. M., Stein, J. M., and Grossblatt, N. eds, <u>Wound healing: Proceedings of workshop</u>.

 Washington, DC: National Academy of Sciences, National Research Council. p. 4.
- Emmons, H. W. 1961. Some observations on pool burning. In: Berl, W. G., ed,

 The use of models in fire research. Washington, DC: National Academy
 of Sciences National Research Council. Publication 786. 50-67.

- Emmons, H. W. 1964. Fundamental problems of the free burning fire. <u>Tenth</u> symposium (international) on combustion. pp. 951-964. Combustion Institute, Pittsburgh, PA.
- Evans, E. I., Brooks, J. W., Schmidt, F. H., Williams, R. C., and Ham, W. T. 1955. Flash burn studies on human volunteers. <u>Surgery</u>. 37:280.
- Feller, I., Flora, J. D., and Bawol, R. 1976. Baseline results of therapy for burned patients. <u>Journal of the American medical association</u>. 236:(17):1943-1947.
- Feller, I., Richards, K., and Crane, K. 1972. The role of flammable fabrics in severe burn injuries. In: Proceedings of the sixth annual meeting of the information council on fabric flammability. Hotel Commodore, 7 December, New York, NY.
- Fisher, J. C., Wells, J. A., and Fulwider, B. T. 1977. Do we need a burn severity grading system? <u>Journal of trauma</u>. 17:252.
- Forbes, P. D. 1969. Vascular supply of the skin and hair in swine. In:
 Montag, W., and Dobson, R. L., eds. <u>Hair growth, advances in biology of skin</u>. Oxford, MA: Pergamon. 9, 479.
- Fowler, J. F. 1963. Experiments with fractionated X-ray treatment of the skin of pigs. <u>British journal of radiology</u>. 36:188-196.
- Gaydon, A. G., and Wolfhard, H. G. 1960. <u>Flames, their structure, radiation</u> and temperature. London: Chapman and Hall Ltd.
- Gillman, T., and Ordman, L., 1966. Histogenesis of healing incised and excised wounds in young pigs. In: Bustad, L.K., and McClellan, R.O., eds. Swine in biomedical research. Seattle, WA: Frayn. p. 299.
- Gordon, W., and McMillen, R. D. 1965. Temperature distribution within aircraft-fuel fires. <u>Fire technology</u>. 1(1):52.
- Grillo, H. D. 1966. Open wounds as an experimental system. In: Levenson, S. M., Stein, J. M., and Grossblatt, N., eds. <u>Wound healing:</u>
 <u>Proceedings of a workshop.</u> Washington, DC: National Academy of Sciences National Research Council. pp. 261-269.
- Griswold, J. 1946. Fuels, combustion, and furnaces. New York, NY: McGraw-Hill.
- Hardy, J. D. 1962. Physiological effects of high intensity infrared heating.

 <u>American society heating and refrigeration engineers journal</u>.
- Hardy, J. D., and Soderstrom, G. F. 1938. Heat loss from the nude body and peripheral blood flow at temperature of 22° to 35°C. <u>Journal of nutrition</u>. 16:493.
- Henriques, F. C. 1947. Studies of thermal injury. V. The predictability and the significance of thermally induced rate processes leading to irreversible epidermal injury. <u>Archives of pathology</u>. 43:489-502.
- Henriques, F. C., and Moritz, A. R. 1947. Studies of thermal injury. I. The condition of heat to and through skin and the temperatures attained therein. A theoretical and an experimental investigation. American journal of pathology. 23:531-549.
- Hinshaw, J. R. 1963. Progressive changes in the depth of burns. Archives of surgery. 87:993-997.

- Hinshaw, J. R., and Payne, F. W. 1963. The restoration and remodeling of the skin after a second degree burn. <u>Surgery, gynecology and obstetrics</u>. 117:738-744.
- Hirschfelder, J. O. 1962. Some remarks on the theory of flame propagation.

 Ninth symposium (international) on combustion. Combustion Insitute,
 Pittsburgh, PA. pp. 553-559.
- Jobb, K. Y. F., and Kennedy, P. C. 1970. <u>Pathology of domestic animals</u>. 2d ed., Vol. 2. New York, NY: Academic Press.
- Karasek, J., and Oehlert, W. 1968a. Die ultrastruktur der epidermis des schweines. I. Stratum basale und stratum spinosum. Zeitschrift fuer mikroskopische anatoische forschung. 78:133.
- ---- 1968b. Die ultrastruktur der epidermis des schweines. II. Stratum granulsoum and corneum. Zeitschrift fuer mikroskopische anatoische forschung. 79:157.
- Knapp, S. C., Allemond, P. A., and Karney, D. H. 1978. Helicopter crashworthy fuel systems and their effectiveness in preventing thermal injury. In: Operational helicopter aviation medicine: AGARD/NATO Panel Specialists' Meeting, May 1-5; Fort Rucker, AL. London: Technical Editing and Reproduction Ltd. pp. 61-1-61-7. AGARD-CP-255.
- Knapp, S. C., and Knox, F. S., III. 1982. Human response to fire and personnel protection measures. AGARD/NATO PEP lecture series no. 123 on "Aircraft fire safety." 7-16 June, at Oslo, Norway, London, England, and Washington, D.C.
- Knox, F. S., III, McCahan, G. R., Jr., Wachtel, T. L., Trevethan, W. P.,
 Martin, A. S., DuBois, D. R., and Keiser, G. S. 1971. Engineering test
 of lightweight underwear of the winter flight clothing system: Thermal
 protection. Fort Rucker, AL: U.S. Army Aeromedical Research
 Laboratory. USAARL Report No. 71-19.
- Knox, F. S., III. 1971. <u>Protective clothing for aviators</u>. Presented at the Third U.S. Army Aviation Accident Prevention Conference; August 18-19; Fort Rucker, AL.
- ----. 1972a. Preliminary results, conclusions and recommendations from the evaluation of helmet flammability DH-132 and T56-6 helmets. Fort Rucker, AL: U.S. Army Aeromedical Research Laboratory. USAARL LR-72-17-3-5.
- ---- 1972b. Realistic evaluation of fabrics for thermal protective clothing. Presented to the Survival and Flight Equipment Association 10th Annual Symposium; October 2-5; Phoenix, AZ.
- Knox, F. S., III, McCahan, G. R., Jr., and Wachtel, T. L. 1972. The use of the pig as a bioassay substrate for evaluation of thermal protective clothing and physical sensor calibration. Presented at the Eighth Scientific Session of the Joint Committee on Aviation Pathology; October 8-12; Colorado Springs, CO. Also presented at the American Burn Association 5th Annual Meeting; 1973 April 6; Dallas, TX (16mm color, sound film, 20 min.). Published in Journal of aerospace medicine. 45:933, 1974.
- Knox, F. S., and Bailey, R. W. 1973. Results, conclusions and recommendations from the evaluation of helmet flammability DH-132 and T56-6 helmets. Fort Rucker, AL: U.S. Army Aeromedical Research Laboratory. USAARL LR-73-9-3-4.

- Knox, T. (F. S., III), and Knapp, S. C. 1975. <u>Testing for thermal protection</u>. Presented at the 4th National Flame-Free Design Conference; March 11-13; San Diego, CA.
- Knox, F. S., III, and Nockton, R. A. 1976. <u>Data analysis and mathematical modeling based on U.S. Army Aeromedical Research Laboratory's experimental porcine burn Phase I data. 1 July 1975 30 September 1976. Shreveport, LA: LSU School of Medicine, Department of Physiology and Biophysics. Contract No. DABT01-75-C-0257.</u>
- Knox, F. S., III, Wachtel, T. L., and Knapp, S. C. 1978a. How to measure the burn-preventive capability of nonflammable textiles: A comparison of the USAARL porcine bioassay technique with mathematical models. <u>Burns</u>. 5(1):19-29. Also reprinted as USAARL Report No. 79-5. (Uses model and sensor output to predict burns.)
- ----. 1978b. Biomedical constraints on thermal protective flight clothing design: A bio-engineering analysis. In: Operational helicopter aviation medicine: AGARD/NATO Panel Specialists' Meeting, May 1-5; Fort Rucker, AL. London: Technical Editing and Reproduction Ltd. pp. 63-1-63-11. AGARD-CP-255.
- postcrash fires as aids in thermal protective clothing design and selection. In: Proceedings of the army science conference; June 20-22; West Point, NY. pp. 267-281. Vol. II (AD-A056437). Also published as USAARL Report No. 78-15.
- Knox, F. S., III, Wachtel, T. L., and McCahan, G. R., Jr. 1978. <u>Evaluation of four thermally protective fabrics using the USAARL bioassay method</u>. Fort Rucker, AL: U.S. Army Aeromedical Research Laboratory. USAARL Report No. 78-9.
- Knox, F. S., III, Wachtel, T. L., Trevethan, W. P., McCahan, G. R., Jr., and Brown, R. J. 1978. A porcine bioassay method for analysis of thermally protective fabrics: A histological and burn depth grading system. Fort Rucker, AL: U.S. Army Aeromedical Research Laboratory. USAARL Report No. 78-11.
- Knox, F. S., III, Wachtel, T. L., McCahan, G. R., Jr., and Knapp, S. C. 1978.
 A porcine bioassay study of the physiological effects of fiber and dye degradation products (FDP) on burn wound healing. Fort Rucker, AL:
 U.S. Army Aeromedical Research Laboratory. USAARL Report No. 78-10.
 Also published as The effect of fiber and dye degradation products (FDP) on burn wound healing. <u>Journal of aviation</u>, space, and enviornmental medicine. October, pp. 1007-1015.
- Knox, F. S., III, Knapp, S. C., McCahan, G. R., Jr., and Wachtel, T. L. 1979. Bioassay determination of thermal protection afforded by candidate flight suit fabrics. <u>Journal of aviation</u>, space and environmental medicine. 50(10):1023-1030.
- Knox, F. S., III. 1979a. <u>VIPER exhaust burn hazard</u>. Fort Rucker, AL: U.S. Army Aeromedical Research Laboratory. USAARL LR-79-9-1-1. (Application of the model BRNSIM to assess the hazard associated with exposure to hot gases.)
- Knox, F. S., III. 1979b. <u>Predictability of burn depth: Data analysis and mathematical modeling based on USAARL's experimental porcine burn data.</u>
 Shreveport, LA: Louisiana State University School of Medicine,
 Department of Physiology and Biophysics. Contract DAMD17-77-7004.

- Knox, F. S. III, Sauermilch, P. W., Wachtel, T. L., McCahan, G. R., Jr., Trevethan, W. P., Lum, C. B., Brown, R. J., and Alford, L. A. 1979. A fire simulator/shutter system for testing protective fabrics and calibrating thermal sensors. Fort Rucker, AL: U.S. Army Aeromedical Research Laboratory. USAARL Report No. 79-4.
- Knox, F. S., III, Wachtel, T. L., and Knapp, S.C. 1980. Burn prediction model for thermally protective clothing evaluation. Presented to the Aerospace Medical Association; 12-15 May; Anaheim, CA.
- Knox, F. S., III, Wachtel, T. L., McCahan, G. R., Jr., and Knapp, S. C. 1986. Thermal properties calculated from measured water content as a function of depth in porcine skin. <u>Burns</u>. 12(8):556-562.
- Kreith, F. 1965. <u>Principles of heat transfer</u>. 2d ed. Scranton, PA: International Textbook Company. Chapter 4.
- Lewis, B., and von Elbe, E. 1947. <u>Temperature: Its measurement and control in science and industry</u>. American Institute of Physics. New York, NY: Reinhold Publishing Corp.
- Lewis, B., Pease, R. N., and Taylor, H. S. 1956. <u>Combustion processes</u>. Vol. II, High speed aerodynamics and jet propulsion. Princeton University Press.
- Lipkin, M., and Hardy, J. D. 1954. Measurement of some thermal properties of human tissues. <u>Journal of applied physiology</u>. 7(2):212-217.
- Lum, C. B. 1972. Trip report: Microscopic burn damage data consultation with Dr. Walter Trevethan. Pensacola, FL: Naval Aerospace Medical Institute; November 27-28.
- Lum, C. B. 1973. <u>Instrumented helicopter burn</u>. Fort Rucker, AL: U.S. Army Aeromedical Research Laboratory. USAARL LR-73-6-3-2.
- Lyon, J. L., Davis, T. P., and Pearse, H. E. 1955. Studies of flash burns:

 The relation of thermal energy applied and exposure time to burn

 severity. Rochester, NY: University of Rochester. Atomic Energy
 Report 394.
- Lyon, J. L., Emery, A. J., Jr., Pearse, H. E., and Davis, T. P. 1955.

 Rochester, NY: University of Rochester. Atomic Energy Project Report UR-401.
- Madden, J. E., Edlich, R. F., Prusak, M., and Wangensteen, O. H. 1971. The molecular basis for the antiseptic activity of rosaniline dyes in the contaminated wound. <u>Surgical forum</u>. 22:63.
- Maggio, R. C. 1956. A molded skin stimulant material with thermal and optical constants approximating those of human skin. New York, NY:
 Naval Materials Laboratory, New York Naval Shipyard. Laboratory Project 5046-3. Part 105.
- Magnus, G. 1961. Tests on combustion velocity of liquid fuels and temperature distribution in flames and beneath surface of the burning liquid. In: Berl, W. G., ed. The use of models in fire research.

 Publication 786. Washington, DC: National Academy of Sciences National Research Council.
- Marcarian, H. Q., and Calhoun, M. L. 1966. Microscopic anatomy of the integument of adult swine. American journal of veterinary research. 27:765.

- McCahan, G. R., Jr., and Wachtel, T. L. 1972. Anesthesia or immobilization of domestic and miniature swine--methods and some problems. Fort Rucker, AL: U.S. Army Aeromedical Research Laboratory. USAARL Report No. 73-6.
- McClellan, P. O. 1968. Application of swine in biomedical research.

 <u>Laboratory animal care</u>. 18:120.
- McCoy, J. A., Micks, D. W., and Lynch, J. B. 1968. Discriminant function probability model for predicting survival in burned patients. <u>Journal of the American medical association</u>. 203:644-646.
- Mehta, A., and Wong, F. 1973. <u>Measurement of flammability and burn potential of fabrics</u>. (Summary Report December 1971 January 1973.) Cambridge, MA: Fuels Research Laboratory, Massachusetts Institute of Technology Project DSR 73884.
- Meyer, W., and Neurand, K. 1976. The distribution of enzymes in the skin of the domestic pig. <u>Laboratory animals</u>. 10:347.
- Mixter, G., and Pearse, H. E. 1953. <u>Studies of flash burns: The protection afforded by 2, 4 and 6 layer fabric combinations</u>. Rochester, NY: The University of Rochester. Atomic Energy Project UR-261.
- Moncrief, J. A. 1969. Burns. In Schwartz, S. I., ed. <u>Principles of surgery</u>. New York, NY: McGraw-Hill, Inc. pp. 205-206.
- Montagna, M., and Yun, J. S. 1964. Skin of the domestic pig. <u>Journal of investigative dermatology</u>. 43:11.
- Montagna, W., and Yun, J. S. 1964. The skin of the domestic pig. <u>Journal international college of surgeons</u>. 42:11-21.
- Moritz, A. R. 1947. Studies of thermal injury. III. The pathology and pathogenesis of cutaneous burns, an experimental study. American journal of pathology. 23:915-941.
- Moritz, A. R., and Henriques, F. C. 1947. Studies of thermal injury. II. The relative importance of time and surface temperature in the causation of cutaneous burns. American journal of pathology. 23:695-720.
- Moritz, A. R., Henriques, F. C, Dutra, F. R., and Weisiger, J. R. 1947.
 Studies of thermal injury, IV, and exploration of the casualty producting attributes of conflagrations, local and systemic effects of
 general cutaneous exposure to excessive circumambient (air) and
 circumradiant heat of varying duration and intensity. Archives of
 pathology. 43:466-488.
- Morse, H., Tichner, G., and Brown, R. 1975. <u>Burn damage and burn depth</u> <u>criteria</u>. Acurea Corp, Mountain View, CA. Aerotherm TN-75-26.
- Morse, H. L., Thompson, J. G., Clark, K. J., Green, K. A., and Moyer, C. B. 1973. Analysis of the thermal responses of protective fabrics. Wright-Patterson Air Force Base, OH: Air Force Materials Laboratory, Air Force Systems Command. Technical Report AFML-TR-73-17.
- Morton, B. R. 1964. Modeling fire plumes. <u>Tenth symposium (international)</u> on combustion. Combustion Institute, Pittsburgh, PA. pp. 973-982.
- Morton, J. H., Kingsley, H. D., and Pearse, H. E. 1952. Studies on flash burns: threshold burns. <u>Surgery, gynecology, and obstetrics</u>. 94:317.

- Moserova, J., Behounkova, E., and Prouza, Z. 1975. Subcutaneous temperature measurements in a thermal injury. Burns. 1:267.
- Neill, D. T., Welker, J. R., and Shepcevich, C. M. 1970. Direct contact heat transfer from buoyant diffusion flames. <u>Journal of fire and flammability</u>. 1:289-300.
- Nielsen, H. J., and Tao, L. N. 1964. The fire plume above a large free-burning fire. <u>Tenth symposium (international) on combustion</u>. Combustion Institute, Pittsburgh, PA. pp. 965-972.
- Pavshkin, Y. M. 1962. <u>The chemical composition and properties of fuels for jet propulsion</u>. New York, NY: Pergamon Press.
- Peacock, E. E., Jr., and Van Winkle, W., Jr. 1970. <u>Surgery and biology of wound repair</u>. Philadelphia, PA: W.B. Saunders Co.
- Perkins, J. B., Pearse, H. E., and Kingsley, H. D. 1951. <u>Studies on flash burns: The relation of the time and intensity of applied thermal energy to the severity of burns</u>. Rochester, NY: University of Rochester.

 Atomic Energy Project Report UR-217.
- Pesman, G. J. September 1953. <u>Appraisal of hazards to human survival in airplane crash fires</u>. National Advisory Committee for Aeronautics Technical Note 2996, Washington DC.
- Pinkel, I. I., Preston, G. M., and Pesman, G. J. August 1952. Mechanism of start and development of aircraft crash fires. National Advisory

 Committee for Aeronautics Research Memorandum E52F06, Washington DC.
- Ragan, H. A., and Gillis, M. F. 1975. Restraint, venipuncture, endotracheal intubation and anesthesia of miniature swine. <u>Laboratory animal</u> sciences. 25:409-419.
- Ragozin, N. A. 1961. <u>Jet propulsion fuels</u>. New York, NY: Pergamon Press.
- Reneau, D. D., and O'Young, N. 1976, 1977, 1978. Consultation report to F. S. Knox. Shreveport, LA: Louisiana State University Medical Center, Department of Physiology and Biophysics. U.S. Army Contract Nos. DABTO1-75-C-0257 and DAMD-17-77-C-7004.
- Robb, H. J. 1967. Dynamics of the microcirculation during a burn. Archives of surgery. 94:776.
- Rushmer, R. F., Buettner, K. J. K., Short, J. M., and Odland, G. F. 1966. The skin. <u>Science</u>. 154(3747):343-348.
- Scapicchio, A. P., Constable, J. D., and Opitz, B. F. 1967. Comparative effects of silver nitrate and sulfamylon acetate on epidermal regeneration. <u>Surgical forum</u>. 18:510.
- Spalding, D. B. 1962. <u>The art of partial modeling</u>. Presented at the Colloquium on Modeling Principles, Ninth Symposium (international) on Combustion. Combustion Institute, Pittsburgh, PA. pp. 833-842.
- Stanton, R. M., Schulman, S., and Ross, J. H. 1973. <u>Evaluation of PBI and Nomex II for Air Force flight suits</u>. Air Force Material Laboratory, Wright-Patterson AFB, Ohio. Technical Report AFML-TR-73-28.
- Stoll, A. M., and Hardy, J. D. 1950. Study of thermocouples as skin thermometers. <u>Journal of applied physiology</u>. II:532-543.

- Stoll, A., and Greene, L. C. 1959. Relationship between pain and tissue damage due to thermal radiation. <u>Journal of applied physiology</u>. 14:373.
- Stoll, A. M. 1962. Thermal protection capacity of aviator's textiles.

 <u>Aerospace medicine</u>. 846-850.
- Stoll, A. M., and Chianta, M. A. 1969. Method and rating system for evaluation of thermal protection. <u>Aerospace medicine</u>. 40(11):1232-1237.
- Stoll, A. M., and Chianta, M. A. 1970. <u>Heat transfer through fabrics</u>, Warminster, PA: Naval Air Development Center, Aerospace Medical Department. NADC-MR-7017.
- Stoll, A. M., and Chianta, M. A. 1971. Heat transfer through fabrics as related to thermal injury.

 Vol 33(7) Nov. 649-670.

 Transactions-New York Academy of Sciences.
- Stoll, A. 1978. Comments made during thermal protective clothing ad hoc working conference (tri-service). Fort Rucker, AL: U.S. Army Aeromedical Research Laboratory; April 3-4.
- Takata, A. N. 1957. Unpublished data prepared by Armour Research Foundation for Air Force Special Weapons Program (AFSWP-1060), Illinois Institute of Technical Research Institution, Chicago, IL.
- Takata, A. N., Rouse, J., and Stanley, T. 1973. <u>Thermal analysis program</u>. Fort Rucker, AL: U.S. Army Aeromedical Research Laboratory. Report No. IITRI-J6286. Contract No. DA13C01-G-0309.
- Takata, A. 1974. Development of criterion for skin burns. <u>Aerospace medicine</u>. 45(6):634-637.
- Thring, M. W. 1952. <u>The science of flames and furnaces</u>. New York, NY: John Wiley and Sons, Inc.
- Torres, M., and Buchan, M. 1972. Crashworthy fuel system mishap data.

 <u>Aviation digest</u>. pp. 44-45.
- Van Wylen, J. G., and Sonntag, R. E. 1960. <u>Fundamentals of thermodynamics</u>.
 New York, NY: John Wiley & Sons, Inc.
- Vincenti, W. G., and Kruger, C. H., Jr. 1965. <u>Introduction to physical gas dynamics</u>. New York, NY: John Wiley & Sons, Inc. Chapter XI.
- Wachtel, T. L., and McCahan, G. R., Jr. 1973. A comparison of methods of preparing porcine skin for bioassay of thermal injury. Fort Rucker, AL: U.S. Army Aeromedical Research Laboratory. USAARL Report No. 73-9.
- Wachtel, T. L., McCahan, G. R., Jr., and Monafo, W. W., Jr. 1977. Fluid resuscitation in a porcine burn shock model. <u>Journal of surgical</u> research. 23:405-414.
- Wachtel, T. L., Knox, F. S., III, and McCahan, G. R., Jr. 1977. Methods of preparing porcine skin for bioassay of thermal injury. <u>Military medicine</u>. 141:536-538.
- Wachtel, T. L., Knox, F. S. III, and McCahan, G. R., Jr. 1978. A porcine bioassay method for analysis of thermally protective fabrics: A clinical grading system. Fort Rucker, AL: U.S. Army Aeromedical Research Laboratory. USAARL Report No. 78-8.

- Waldron, E. T., Smith, W. F., and Mahen, M. E. 1967. <u>Effectiveness of aviators' garments in protecting against gasoline fires</u>. Natick, MA: U.S. Army Natick Laboratories.
- Waldron, E. T., Smith, W. F., and Mahen, M. E. <u>The protection provided by winter aviators' garments during escape through JP-4 fuel fires</u>.

 Natick, MA: U.S. Army Natick Laboratories. In press.
- Weaver, J. A., and Stoll, A. M. 1969. Mathematical model of skin exposed to thermal radiation. <u>Aerospace medicine</u>. 40:24-30.
- Weinstein, G. D. 1966. Comparison of turnover time of keratinous protein fractions in swine and human epidermis. In: Bustad, K.L., and McClellan, R.O., eds. Swine in biomedical research. Seattle, WA: Frayn.
- Zilioli, A. E. 1971a. <u>Crash injury economics: The costs of training and maintaining on Army aviator</u>. Fort Rucker, AL: U.S. Army Aeromedical Research Laboratory. USAARL Report No. 71-17.
- ----. 1971b. Crash injury economics: Aircrewman injury and death costs occurring in UH-1 Army aircraft accidents in fiscal year 1969. Fort Rucker, AL: U.S. Army Aeromedical Research Laboratory. USAARL Report No. 71-18.

Appendix A

ANALYTICAL MODEL

Several years ago Weaver and Stoll (1969) proposed an extension of Stoll's earlier model (Stoll and Greene, 1959) to heat fluxes higher than those used in obtaining the experimental data upon which the earlier model had been based. They also found that the effective conductivity changed during the exposure and subsequent cooldown period. Takata (1974), using preliminary data from USAARL's Thermal Project (the uncorrected version of the current data base), formulated a model which not only predicted threshold burns but deep burns and tissue water boiling as well. Building on the work of Henriques (1947), Stoll and Greene (1959), Weaver and Stoll (1969), Mehta and Wong (1973) and Takata (1974), an analytical model was formulated as follows:

For the thermal exposure of interest, skin is essentially opaque to thermal radiation and can be considered to transfer energy internally by conduction only, since exposure durations are no longer than the minimum response times reported for increased thermoregulatory system activity (1954). Consequently, thermal energy transfer in skin can be described by the heat conduction or Fourier equation be written as follows:

$$\rho Cp \frac{\partial T}{\partial t} = \frac{\partial}{\partial x} \left(K \frac{\partial T}{\partial x} \right) + q \tag{1}$$

where,

 ρ = density, gm/cm³

Cp = heat capacity, cal/gm-°C

K = thermal conductivity, cal/cm-sec-°C

T = temperature, °C

x = distance, cm

q = energy source, for the first nodal volume, cal/cm^3-sec

^{&#}x27;Simplifying assumption base on the predominance of the radiate mode of heating. May be less valid with fabrics. In actuality a correction is made to q to account for convective heating, surface absorptivity, and attenuation of radiant heating by hair.

Since skin is considered to be opaque to radiant energy from a post crash fire, and since the source term is due only to radiant energy, equation (1) applies only to the surface of the skin. For all conditions in which x > 0, equation (1) reduces to the following:

$$\rho \quad Cp \frac{\partial T}{\partial t} = \frac{\partial}{\partial x} \left(K \frac{\partial T}{\partial x} \right) \tag{2}$$

Solution of equation (1) and (2) requires two boundary conditions for x, preferably at x=0 and x=L, and initial conditions at t=0 for all positions 0 < x < L. If one assumes that there is no backward flux of thermal energy at x=0 (all conduction is into the skin), then the energy flux at x=0 is zero and, consequently, $\partial T/\partial x=0$. Similarly, if the problem assumes that an adiabatic backwell condition prevails at x=L, the fatty tissue, then the net flux out of the system at x=L is 0, or $\partial T/\partial x=0$. These two boundary conditions indicate that the system is closed and that all thermal energy added to the system, $0 \le x \le L$, is distributed within the system and cannot escape.

Initial conditions are established by specifying a uniform temperature for all locations, $0 \le x \le L$ at time t = 0.

Consequently, the system may be defined by the following mathematical model:

$$\rho \ Cp \frac{\partial T}{\partial t} = \frac{\partial}{\partial x} \left(K \frac{\partial T}{\partial x} \right) + q \qquad \qquad & x = 0 : surface \qquad (3a)$$

$$\rho Cp \frac{\partial T}{\partial t} = \frac{\partial}{\partial x} \left(K \frac{\partial T}{\partial x} \right) \qquad \qquad \textcircled{2} 0 \le x \le L$$

 $T_x = CORE TEMPERATURE = TEMPIO + TEMPB$

$$T = T_0$$
, $0 \le x \le L$, $t = 0$ Initial Conditions (4)

$$\frac{\partial T}{\partial x} = 0, \ x = 0, \ 0 \le t \le x \qquad Boundary \ Conditions \ 1 \tag{5}$$

$$\frac{\partial T}{\partial x} = 0, \ x = L, \ 0 \le t \le x \qquad Boundary \ Conditions \ 2 \tag{6}$$

Solution of mathematical model (Reneau and O'Young, 1976, 1977, 1978)

An analytical solution to equation set (3) was not considered feasible due to the variable nature of q, Cp and K, so explicit differencing methods of numerical analysis were employed to solve the equations. Several investigators working with linear systems have found that the Crank- Nicholson six point implicit differencing method provided an excellent numerical solution (Crank and Nicholson, 1947). For the solution of equation set (3) of the mathematical model, it was decided to apply the Crank-Nicholson method to the second order partial derivatives and corresponding explicit methods to the first order partials.

The grid work in Figure A-1 is a representative of the differenced system from x = 0 to x = L (j's) and t = 0 to $t = \tau$ (i's).




Figure A-1. Gridwork for numerical analysis

The Crank-Nicholson technique involves averaging the value of the dependent variable over the i and i+1 row at a constant j position. The second order derivative is then evaluated at the (j, i+1/2) position. A forward difference formulation is applied to the term to match the same position.

The above described implicit differencing method is noted for the characteristics of stability and convergence. Correct increment sizes yield reliable convergence. The model was implemented in FORTRAN IV using solution techniques of Thomas as described by Bruce et al. (1953).

This initial model was revised to allow energy flux across the surface, x = 0, during heating, convective heat loss at the skin surface during cooling and heat transfer into deep tissues including conduction into fat, convective cooling via the blood, tissue water boiling, a temperature gradient from surface to fat and a gradient of thermal properties based on measured tissue water. The model, BURNSIM, is a run interactively with the following variables changeable for each run:

Table A-1 Model parameters changeable interactively

INPUTS

TEMPIO = Initial surface temperature, °C; nominally 32.5 °C for man

DENS = Density of skin, 1.0 gm/cm^3

Q1 = Incident heat flux either constant or as a file of fluxes, cal/cm²-sec

BL = Skin thickness, $2200\mu m$ (The last $200\mu m$ is considered to be fat)

AK = Calculation interval, nominally .01 sec. For short exposures, the calculation interval must be at least one hundred times less than the exposure duration.

JINC = Number of nodes, nominally 12

TEMPB = Differences between TEMPIO and backwall (fat/core)
temperature, °C. Note: TEMPIO + TEMPB = core temperature

Absorb = Absorptivity usually 0.613 assuming 10 percent convective, 90 percent radiative heating, and 5 percent of radiation intercepted by hair

Boil = Temperature when water boiling occurs, 100.15 °C

ETIME = Exposure time, seconds

ITIME = Maximum calculation time, usually 80-100 seconds

Nxtra = Number of extra nodes between the surface and node #2 at $200\mu\text{m}$, initially set at seven, used for superficial burns Note: The seventh node must be at $175\mu\text{m}$ for an accurate time to pain prediction.

Blood = Factor to adjust amount of convective cooling by blood usually set at 0.001

DE1 & DE2 = ΔE/R from Arrehenius relationship for tissue temperatures from 44°C to 50°C, or over 50°C, respectively

PL1, PLN1, or PL2 and PLN2 => log P = logN + ylog10 = PL + PLN for tissue temperatures from 44°C to 50°C, or over 50°C, respectively

Damage Rate Constants: PL1, PLN1, PL2, PLN2, DE1, DE2 (for Nodes 2-12)
APL1, APLN1, APL2, APLN2, ADE1, ADE2 (for Nodes 1 and Xtra
Nodes)

Cp(J) = Heat capacity as a function of depth, (J)

BK(J) = Thermal conductivity as a function of depth, (J)

PCWATER = Percent water at a skin depth of $10\mu m$ at 60 percent relative humidity

WATER(J) = Percent water at each node based on 60 percent relative
 humidity

OUTPUTS

Flux (I) - tabulated heat flux as a function of time

DAMAGE, W, at each depth (Node)

Maximum temperature

Threshold depth in μ m (microns)

Final time - total calculation time

Time to pain

File of calculated temperatures for later plotting by ${\tt HARVARD}$ GRAPHICS

File summarizing simulation

File of temperature as printed each second on the terminal

From the relationship for first order kinetics assumed to apply in damaging tissue protein we have:

damage rate=
$$\frac{d\Omega}{dt}$$
=Pe^{- $\Delta E/RT$} ;

total =
$$\int \frac{ETIME}{d\Omega/dt} + \int \frac{ITIME}{d\Omega/dt}$$
 (8) damage 0 ETIME

if $P = N \times 10^{y}$ and $\Delta E/R = DE$

then:

$$\ln \frac{dw}{dt} = \ln N + y \ln 10 - \frac{\Delta E}{R} \cdot \frac{1}{T} = PL + PLN - DE \cdot \frac{1}{(T+273)}$$
 (9)

Thus for damage calculations the following constants are entered:

$$PL_1 (44^{\circ}C - 50^{\circ}C) = 1.46$$
 $PL_2 (50^{\circ}C - 100^{\circ}C) = 2.24$

PLN,
$$(44^{\circ}C - 50^{\circ}C) = 147.37$$
 PLN, $(50^{\circ}C - 100^{\circ}C) = 239.47$

$$DE_1 (44^{\circ}C - 50^{\circ}C) = 50,000$$
 $DE_2 (50^{\circ}C - 100^{\circ}C) = 80,000$

The program outputs $d\Omega/dt$, for each node at each time step, total is damage for each node and a threshold depth, where $\Omega=1$. This depth, found using inverse interpolation on two or three Ω s nearest 1 using either y or $\log(y)$.

Since the first presentations (Knox, Wachtel, and Knapp, 1978a, 1978c) BURNSIM has under gone further development.

Thermal properties of skin

Measurements of the water content of pig skin as a function of thickness were made on split thickness skin samples from several pigs.

Give a table of measured values of water content as a function of skin thickness, a least-square cubic polynomial was fit to the data and water content as a function of depth was computed from the formula:

$$W(T-d) = \frac{T}{d}(W_T - W_{T-d}) + W_{T-d}$$
 (10)

where T is the total thickness of a slab, W_T is the fraction of water computed from the cubic equation, d is the thickness of a thin slab at a depth T-d, and W_{T-d} is the fraction of water above the thin slab.

Thermal properties of the tissue were computed from the equations (Cooper and Trezek, 1971):

1) density:
$$\gamma = \left[\frac{W_w}{\gamma_w} + \frac{W_f}{\gamma_f} + \frac{W_p}{\gamma_p}\right]^{-1}$$
 (11)

2) heat capacity:
$$Cp = W_u Cp_u + W_c Cp_t + W_n Cp_n$$
 (12)

3) thermal conductivity:
$$K = \gamma \left[\frac{k_w W_w}{\gamma_w} + \frac{k_f W_f}{\gamma_f} + \frac{k_p W_p}{\gamma_p} \right]$$
 (13)

where the subscripts w, f, and p refer to water, fat, and protein, respectively. W_n is the mass fraction, γ_n the density, Cp_n the heat capacity, and k_n the thermal conductivity of the respective components. Values of the various terms used were:

$$\gamma_w = 1 \text{ gm/cm}^3$$
 $Cp_w = 1 \text{ cal/gm-'C}$ $k_w = 1.5 \text{X} 10^{-3} \text{ cal/cm-sec-'C}$

$$\gamma_p = 1.54 \text{ gm/cm}^3$$
 $Cp_p = 0.26 \text{ cal/gm-'C}$ $k_p = 4.3 \text{X} 10^4 \text{ cal/cm-sec-'C}$

Fat and protein were assumed to be present in equal amounts so that:

$$W_{f} = W_{p} = (1 - W_{w})/2, \qquad (14)$$

and the resultant equations were:

$$\gamma = (6.18277X10^{-2} W_w + .938172)^{-1}$$
 (15)

$$K = \gamma (1.08432X10^{-3} W_w + 4.15684X10^{-4})$$
 (16)

$$Cp = .595 W_w + .405$$
 (17)

Using the equations above, the profile of thermal properties was calculated for skin depths of from 80 to $2000\mu m$. A linear extrapolation of tissue water content from a depth of $80\mu m$ to the skin surface was made using a stratum corneum water content calculated from Rushmer et al. (1966) and the ambient percent humidity during the experimental phase of the project. This calculated water profile was used to complete the calculation of thermal properties profile from $80\mu m$ to the skin surface. The thermal properties of the skin at $2200\mu m$ were assumed to be those of fat. These new thermal properties replaced those chosen by Morse et al. (1973) and used during previously reported simulations (Knox, Wachtel, and Knapp, 1978a, 1978c). See the paper entitled "Thermal properties calculated from measured water content as a function of depth in porcine skin" (Knox et al., 1986).

Intraskin temperatures

In earlier simulations (Knox et al, 1978a, 1978c) it became apparent that unless the temperature calculations reasonably represented what actually occurred in the skin, adjustment of the values for PL, PLN and DE in the damage equation to match a few data points would not be likely to result in a model which works well for all cases. Fortunately

11 intraskin temperature profiles were recorded on FM magnetic tape. These voltage records were digitized and converted to tables of temperatures at 100 samples per second. Figure A-2 presents the one page summary report from a simulation of the exposure of Pig 294RF to a 3.47 cal /cm²-sec fire for 3.02 seconds. Note that boiling occurred (confirmed by blister formation, Figure A-3) and that the surface reached a maximum of 128.724°C. Predicted threshold depth was $1520\mu m$. Three observed temperature profiles are overlayed on the calculated temperature profiles (for nodal depths of 0, 200, $400....2200\mu m$) in Figures A-4, A-5, and A-6. The oscillations in the observed temperature profile are most probably due to a "hunting" in the autoregulation of tissue perfusion by blood. The frequency, for example, is similar to that seen in studies of microcirculation.

MODEL NAME OR DESCRIPTION: PIG 294RF ABS 0.613

SKIN DIFFUSION DATA INPUT PARAMETER LIST

TEMPIO=	34.9700		1.00000	Q1=	3.47000
BL= .2	220000		00000E-01	JINC=	12
TEMPB=	3.3600		.613000	BOIL=	100.150
APL1=	.780000	APLN1=	285.520	ADE1=	93534.9
APL2=	.600000	APLN2=	117.430	ADE2=	39109.8
PL1= PL2= ETIME= BLOOD=	1.46 2.24 3.02 .0010	PLN1= PLN2= ITIME=	147.37 239.47 80.00	_	50000.00 80000.00 8

EXTRA NODES: 22.2 44.4 66.7 88.9 111.1 133.3 155.6 177.8

FLUX FILE I.D.:

.00 2

FLUX(I)= 1 3.470 2 3.470

W= .39950E+01 W= .40733E+00 W= .45290E-01 D= .72442E+01 D= .73778E+01 D= .74955E+01

V	=	.19755E+19	AT DEPT	(IN MICRONS)=	.112535E-06
W	= -	.82482E+12	AT DEPT	i (IN MICRONS)=	200.000
W.	=	.26532E+09	AT DEPT	I (IN MICRONS)=	400.000
V	=	.57713E+06	AT DEPT	H (IN MICRONS)=	600.000
Ŵ	=	.84775E+04	AT DEPT	H (IN MICRONS)=	800.000
V	=	.44473E+03	AT DEPT	I (IN MICRONS)=	1000.00
W	=	.39319E+02		H (IN MICRONS)=	1200.00
V	=	.39950E+01	AT DEPT	H (IN MICRONS)=	1400.00
W	=	.40733E+00	AT DEPT	H (IN MICRONS)=	1600.00
W	=	.45290E-01	AT DEPT	H (IN MICRONS)=	1800.00
W	=	.89902E-02	AT DEPT	H (IN MICRONS)=	2000.00
W	=	.00000E+00	AT DEPT	H (IN MICRONS)=	2200.00

MAXIMUM TEMPERATURE = 128.724

THRESHOLD DEPTH =

1528.

FINAL TIME = 80.00

Figure A-2. Summary report for simulation of Pig 294RF to a 3.47 cal/cm²-sec fire for 3.02 seconds.






Figure A-3. Intraskin thermocouple (0.003", "located superficially") shown prior to burn (left) and subsequent to exposure to 3.47 cal*cm²*sec¹ for 3.02 seconds (right).

Gross grade = 13 New micro grade = 8 Threshold depth = $1465\mu m$




Figure A-4. Predicted skin temperature at each node (solid lines) and measured intraskin temperature in pig 284 location #27 when exposed to 3.47 cal.cm⁻²·sec⁻¹ for 3.02 seconds




Figure A-5. Predicated skin temperature at each node (solid lines) and measured intraskin temperature in pig 284 location #28 when exposed to 3.47 cal·cm $^{-2}$ ·sec $^{-1}$ for 3.02 seconds




Figure A-6. Predicated skin temperature at each node (solid lines) and measured intraskin temperature in pig 284 location #29 when exposed to 3.47 cal·cm⁻²·sec⁻¹ for 3.02 seconds

APPENDIX B

C	Last Edited March 5, 1992				
C	******************* 12-POINT BURN PREDICTION MODEL***********				
_					
С	PROGRAM BURNSIM ! BURN PREDICTION MODEL WITH WATER BOILING				
С	! AND USE OF EITHER CONSTANT OR TABULATED FLUX				
С	! AND VARIABLE COOLING BY BLOOD FROM NODES 2				
C	! AND 3 BEGINNING AT .01 SEC AND LINEARLY				
C	! INCREASING TO 20 SEC AND THEN REMAINING				
C	! CONSTANT				
С	! CHANGED TO DO INTEGRATION OF DAMAGE W & XW				
С	! WITHIN PROGRAM AND NOT OUT TO DISK AND BACK				
_					
C	! CHANGED TO INCORPORATE THE CHANGES IN MODEL				
C	! 7 NAMELY DIFFERENT RATE CONSTANTS ETC FOR				
С	! SUPERFICIAL NODES AND VARIABLE AK IN BLUD				
С	THIS MODEL WAS DEVELOPED UNDER CONTRACT FOR THE U.S. ARMY				
C	MEDICAL RESEARCH AND DEVELOPMENT COMMAND, AND THE U.S. ARMY				
C	AEROMEDICAL RESEARCH LABORATORY, FORT RUCKER AL. 36362,				
c	STANLEY C. KNAPP, COL, MC, COMMANDING, BY FRANCIS S. KNOX, III,				
C	PH.D. WITH THE ASSISTANCE OF DANIEL D. RENEAU, PH.D., NELSON				
C	O'YOUNG, AND CHET ELLIS, M.S.				
_	0 1001.0, 12.0 01.22 22.23, 1.00				
С	ADDITIONAL DEVELOPMENT CONDUCTED UNDER ILIR FUNDING AT USAARL				
С	AND ON OWN TIME BY FRANCIS S. KNOX, III, PH.D.				
	·				
C	QUESTIONS AND COMMENTS SHOULD BE ADDRESSED TO:				
C	FRANCIS S. KNOX, III, PH.D				
C	CHIEF, ESCAPE AND IMPACT PROTECTION BRANCH				
С	BIODYNAMICS AND BIOCOMMUNICATIONS DIVISION				
С	ARMSTRONG LABORATORY				
C	WRIGHT-PATTERSON AIR FORCE BASE, OHIO 45433				
C	COM. 513-255-3931 AV 785-3931				
_					
C	This copy current working copy of Dr. Knox. Other copies				
C	are not to be further distributed without permission from				
C	Dr. Knox.				
с					
	INCLUDE 'FGRAPH.FI' INCLUDE 'FGRAPH.FD'				
	REAL*4 ITIME, NOFIL, TP, SUM(13), DW(13) INTEGER CHANGE, PTS, AGAIN, PROCED				
	INTEGER CHANGE, PIS, AGAIN, PROCED INTEGER*4 DUMMY4				
	INTEGER*4 DUMMY2				
	DIMENSION T(12),F(12),G(12),H(12),W(12),Z(12),SV(12),U(12)				
	DIMENSION T(12),F(12),G(12),H(12),W(12),Z(12),SV(12),U(12) DIMENSION CP(12,2),BK(12,2),D(12),DSCRPT(20)				
	DIMENSION CF(12,2),BK(12,2),D(12),DSCRF1(20) DIMENSION ID(4),FLUX(600),Q(12)				
	STIMUSTON ID(T)/IIDON(OUO)/Y(IZ)				

```
DIMENSION XTIME(12), ZTIME(12), IFLAG(12), JFLAG(12)
      DIMENSION WATER(12,2), ROCON(2), THCON(2), CPCON(2)
      DIMENSION XW(8), XTRA(8), XTRALG(8), XTMP(8), XDW(8), XSUM(8)
      CHARACTER RESP*1, FILNAM*8, SUMFILE*8, PROFILE*8, TFILE*8
      EQUIVALENCE (NOFIL, IBLNK)
        DATA NOFIL/'
        DATA MAXDIM/12/,D2/200./
        DATA THCON/1.084316E-3,4.1568401E-4/
        DATA ROCON/6.1827743E-2,0.93817226/
        DATA CPCON/0.595,0.405/
C
        LOGICAL UNIT 1 INPUT : 'REN12.DAT'; INITIAL VALUES OF PARAMETERS
        LOGICAL UNIT 1 SCRATCH: VALUES OF XW (IF COMPUTED)
C
C
        LOGICAL UNIT 2 SCRATCH: VALUES OF W (COMPUTED)
C
        LOGICAL UNIT 3 OUTPUT : PROFILE; TEMPERATURE PROFILES
C
        LOGICAL UNIT 4 INPUT : FILNAM; NAME OF FLUX FILE
C
        LOGICAL UNIT 4 OUTPUT: TFILE; DATA FOR PLOTTING TEMPERATURE
C
                                   PROFILES
C
        LOGICAL UNIT 7 OUTPUT : SUMMARY PRINTOUT
C*******Introduction to BURNSIM
        CALL COLORS
        DUMMY4=SETBKCOLOR( $BLUE )
        CALL WELCOME (PROFILE)
C*****Read REN12.DAT input file
        CALL READDATA (TEMPIO, DENS, QO, BL, AK, BOIL, ABSORB, JINC, TEMPB,
       ITIME, ETIME, PCWATR, BLOOD, CP, BK, PL2, PLN2, PL1, PLN1, DE2, DE1,
     + APL1, APLN1, APL2, APLN2, ADE1, ADE2, WATER)
        OPEN (UNIT=1, FORM='UNFORMATTED', STATUS='SCRATCH')
        OPEN(UNIT=2, FORM='UNFORMATTED', STATUS='SCRATCH')
        OPEN(UNIT=3, FILE=PROFILE, FORM='FORMATTED', STATUS='UNKNOWN')
        FLUX(1) = Q0
        FLUX(2) = Q0
        NFLX = 2
        FILNAM = NOFIL
        PPL1 = PL1
        PPLN1 = PLN1
        DDE1 = DE1
        APPL1 = APL1
        APPLN1 = APLN1
        ADDE1 = ADE1
        NXTRA = 0
        NXTRAO = NXTRA
C******Display input values on screen
        CALL SHOWVALUE (TEMPIO, DENS, FLUX, BL, AK, JINC, TEMPB,
     + ABSORB, BOIL, PL1, PLN1, DE1, PL2, PLN2, DE2, ETIME, ITIME, NXTRA,
     + BLOOD, APL1, APLN1, ADE1, APL2, APLN2, ADE2, K, XTRA)
        DO WHILE (AGAIN .EQ. 0)
         CALL PROCEED (RESP, PROCED, AGAIN)
         IF (PROCED.EQ.O) THEN
          PTS=1
          TIME=0.
```

```
CHANGE=0
          MN=0
          CALL clearscreen ( $GCLEARSCREEN )
          WRITE(*,10)
10
       FORMAT(//,15x,'TYPE THE NUMBER OF THE FUNCTION BELOW THAT YOU',/
     + ,15X,'WISH TO PERFORM.',///,20X,'CHOOSE A FUNCTION NUMBER: ',/,
     + 25X,'1 - CHANGE SELECTED INITIAL VALUES',/,25X,'2 - NO CHANGES',
     + '--CONTINUE RUNNING THE PROGRAM',/,25X,'3 - EXIT',//,20X,'PLEASE'
     + ' ENTER THE FUNCTION NUMBER: '$)
          READ(*,20)IANSR
20
       FORMAT(12)
          CALL clearscreen ( $GCLEARSCREEN )
          IF(IANSR.EQ.1) THEN
           DOWHILE (CHANGE.EQ.0)
            CALL SHOWVALUE (TEMPIO, DENS, FLUX, BL, AK, JINC, TEMPB,
     + ABSORB, BOIL, PL1, PLN1, DE1, PL2, PLN2, DE2, ETIME, ITIME, NXTRA,
     + BLOOD, APL1, APLN1, ADE1, APL2, APLN2, ADE2, K, XTRA)
            WRITE(*,30)
       FORMAT(///,15X,'DO YOU WANT TO MAKE ANY CHANGES? TYPE Y/N '$)
30
            READ(*,40)RESP
40
       FORMAT(A1)
            IF(RESP.EQ.'Y'.OR.RESP.EQ.'y') THEN
             CALL CLEARSCREEN ( $GCLEARSCREEN )
             WRITE(*,50)
50
       FORMAT(/T5,'PICK A NUMBER',//T10,'1=TEMPIO',T30,'8=ETIME',//
     + T10,'2=DENS',T30,'9=PL1',/T10,'3=Q1',T30,'10=PLN1',//
     + T10,'4=BL',T30,'11=PL2',/T10,'5=AK',T30,'12=PLN2',//
     + T10,'6=JINC',T30,'13=DE1',/T10,'7=TEMPB',T30,'14=DE2',//
     + T10,'15=ITIME',T30,'16=ABSORBTIVITY'//
     + T10,'17=BOIL',T30,'18=EXTRA NODES'//
     + T10,'19=BLOOD',T30,'20=APL1'//
     + T10,'21=APLN1',T30,'22=APL2'//
     + T10, '23=APLN2', T30, '24=ADE1', T55, '25=ADE2', /, 9X, $)
             READ (*, 20) INUM
             IF(INUM.EQ.1) THEN
              WRITE(*,60)TEMPIO
       FORMAT(//,9X,'THE VALUE FOR TEMPIO IS: ',F10.5,' INPUT NEW VALU'
60
     + 'E: '$)
              READ(*,70)TEMPIO
70
      FORMAT(G10.5)
             ELSEIF(INUM.EQ.2) THEN
              WRITE(*,80)DENS
80
       FORMAT(//,9X,'THE VALUE FOR DENS IS: ',F10.5,' INPUT NEW VALUE: '
     + $)
              READ(*,70)DENS
             ELSEIF(INUM.EQ.3) THEN
              WRITE(*,90)
90
       FORMAT(//,9X,'ENTER THE FLUX FILE NAME (TYPE A <CR> IF NO FILE '
     + ,/,9X,'IS TO BE USED): '$)
              READ(*,100)FILNAM
100
       FORMAT (A8)
C*****Read in flux file
```

```
IF (FILNAM.NE.NOFIL) THEN
               WRITE(*,110)
       FORMAT(/,9X,'ENTER FLUX ID (UP TO 8 CHARACTERS): '$)
110
               READ(*,120)
120
       FORMAT (4A2)
               WRITE(*,130)
130
       FORMAT(/,9x,'ENTER THE NUMBER OF POINTS IN FLUX FILE: '$)
               READ(*,*) NFLX
                DO WHILE (NFLX .GT. 600)
                 WRITE(*,140)
       FORMAT(/,9x,'THE FLUX FILE MUST CONTAIN NO MORE THAN 600 DATA'
140
     + ,/,9X,'POINTS. REENTER A NUMBER LESS THAN OR EQUAL TO 600. '$)
                 READ(*,*) NFLX
                END DO
                WRITE(*,150)
150
       FORMAT(/,9X,'ENTER THE SAMPLE INTERVAL IN SECONDS: '$)
                READ(*,*)TDELT
                OPEN(UNIT=4, FILE=FILNAM, FORM='FORMATTED', STATUS=
     + 'OLD')
                READ(4,*) (FLUX(I), I=1, NFLX)
                CLOSE (4)
                 IF(NFLX.LE.O) STOP 'ERROR----TOO FEW FLUX POINTS.'
                WRITE(*,430)ID,TDELT,NFLX
               ELSE
                WRITE(*,160)FLUX(1)
160
       FORMAT(//,9X,'CONSTANT Q-VALUE = ',F10.5,' INPUT NEW VALUE: '
     + $)
                READ(*,70)FLUX(1)
                FLUX(2) = FLUX(1)
                NFLX = 2
                DO I=1,4
                 ID(I) = IBLNK
                END DO
               END IF
             ELSEIF (INUM. EQ. 4) THEN
              WRITE(*,170)BL
170
       FORMAT(//,9X,'THE VALUE FOR BL IS: ',F10.5,' INPUT NEW VALUE: '
     + $)
              READ(*,70)BL
             ELSEIF(INUM.EQ.5) THEN
              WRITE(*,180)AK
180
       FORMAT(//,9X,'THE VALUE FOR AK IS: ',F10.5,' INPUT NEW VALUE: '
     + $)
              READ(*,70)AK
             ELSEIF(INUM.EQ.6) THEN
              WRITE(*,190)JINC
190
       FORMAT(//,9X,'THE VALUE FOR JINC IS: ',130,' INPUT NEW VALUE: '
     + $)
              READ(*,20)JINC
              IF (JINC.GT.MAXDIM) JINC=MAXDIM
             ELSEIF (INUM. EQ. 7) THEN
            WRITE (*, 200) TEMPB
```

```
200
       FORMAT (//,9X,'THE VALUE FOR TEMPB IS: ',F10.5,' INPUT NEW VA'
     + 'LUE: 'S)
               READ(*,70)TEMPB
              ELSEIF(INUM.EQ.8) THEN
               WRITE(*,210)ETIME
210
       FORMAT(//,9X,'THE VALUE FOR ETIME IS: ',F10.5,' INPUT NEW VALU'
     + 'E: '$)
               READ(*,70)ETIME
             ELSEIF(INUM.EQ.9) THEN
               WRITE(*,220)PL1
220
       FORMAT(//,9X,'THE VALUE FOR PL1 IS: ',F10.5,' INPUT NEW VALUE'
     + ': '$)
              READ(*,70)PL1
              PPL1=PL1
             ELSEIF (INUM. EQ. 10) THEN
              WRITE(*,230)PLN1
230
       FORMAT(//,9X,'THE VALUE FOR PLN1 IS: ',F10.5,' INPUT NEW VALU'
     + 'E: '$)
              READ(*,70)PLN1
              PPLN1=PLN1
             ELSEIF(INUM.EQ.11) THEN
              WRITE(*,240)PL2
       FORMAT(//,9X,'THE VALUE FOR PL2 IS: ',F10.5,' INPUT NEW VALUE'
240
     + ': '$)
              READ(*,70)PL2
             ELSEIF(INUM.EQ.12) THEN
              WRITE(*,250)PLN2
250
       FORMAT(//,9X,'THE VALUE FOR PLN2 IS: ',F10.5,' INPUT NEW VALUE'
     + ': '$)
              READ(*,70)PLN2
             ELSEIF(INUM.EQ.13) THEN
              WRITE(*,260)DE1
260
       FORMAT(//,9X,'THE VALUE FOR DE1 IS: ',F10.1,' INPUT NEW VALUE'
     + ': '$)
              READ(*,70)DE1
              DDE1=DE1
             ELSEIF (INUM. EQ. 14) THEN
              WRITE(*,270)DE2
270
       FORMAT(//,9X,'THE VALUE FOR DE2 IS: ',F10.1,' INPUT NEW VALUE'
     + ': '$)
              READ(*,70)DE2
             ELSEIF (INUM. EQ. 15) THEN
              WRITE(*,280)ITIME
280
       FORMAT(//,9X,'THE VALUE FOR ITIME IS: ',F10.5,' INPUT NEW VALU'
     + 'E: '$)
              READ(*,70)ITIME
             ELSEIF(INUM.EQ.16) THEN
              WRITE(*,290)ABSORB
290
      FORMAT(//,9X,'THE VALUE FOR ABSORB IS: ',F10.5,' INPUT NEW VAL'
     + 'UE: '$)
              READ(*,70)ABSORB
             ELSEIF (INUM. EQ. 17) THEN
```

```
WRITE(*,300)BOIL
300
       FORMAT(//,9X,'THE VALUE FOR BOIL IS: ',F10.5,' INPUT NEW VALUE'
     + ': '$)
              READ(*,70)BOIL
             ELSEIF (INUM. EQ. 18) THEN
              NXTRAO = NXTRA
              WRITE(*,310)NXTRA
310
       FORMAT(//,9X,'THE NUMBER OF EXTRA NODES IS: ',14,' INPUT NEW'
     + ' VALUE: '$)
              READ(*,20)NXTRA
               IF (NXTRA.NE.O) THEN
               IF (NXTRA.GT.8) NXTRA=8
                IF (NXTRAO.NE.O) WRITE(*,320) (XTRA(I),I=1,NXTRAO)
320
       FORMAT(/,9X,'CURRENT EXTRA NODES: ',8F6.1)
               WRITE(*,330)
330
       FORMAT(//,9X,'ENTER NEW VALUES SEPARATED BY COMMAS, OR A <CR> '
     + ,/,9X,'IF THE PROGRAM IS TO CALCULATE VALUES. 'S)
               READ(*,340)XTRA
340
       FORMAT (8G6.1)
               IF (XTRA(1).LE.O) THEN
C******Numerator in next statement is specific for n-point model
                DXTRA = D2/(NXTRA+1)
                DO I=1, NXTRA
                 XTRA(I) = DXTRA*I
                END DO
               END IF
               DO I=1, NXTRA
                XTRALG(I) = ALOG(XTRA(I))
               END DO
              END IF
              NXTRAO = NXTRA
             ELSEIF(INUM.EQ.19) THEN
              WRITE(*,350)BLOOD
350
       FORMAT(//,9X,'THE VALUE FOR BLOOD IS: ',F10.5,' INPUT NEW VALU'
     + 'E: 'S)
              READ(*,70)BLOOD
             ELSEIF(INUM.EQ.20) THEN
              WRITE(*,360)APL1
360
       FORMAT(//,9X,'THE VALUE FOR APL1 IS: ',F10.5,' INPUT NEW VALUE'
     + ': '$)
              READ(*,70)APL1
             ELSEIF(INUM.EQ.21) THEN
              WRITE(*,370)APLN1
370
       FORMAT(//,9X,'THE VALUE FOR APLN1 IS: ',F10.5,' INPUT NEW VALU'
     + 'E: '$)
              READ(*,70)APLN1
             ELSEIF (INUM. EQ. 22) THEN
              WRITE(*,380)APL2
380
       FORMAT(//,9X,'THE VALUE FOR APL2 IS: ',F10.5,' INPUT NEW VALUE'
     + ': '$)
              READ(*,70)APL2
             ELSEIF(INUM.EQ.23) THEN
```

```
WRITE(*,390)APLN2
       FORMAT(//,9x,'THE VALUE FOR APLN2 IS: ',F10.5,' INPUT NEW VALU'
390
     + 'E: '$)
               READ (*, 70) APLN2
              ELSEIF(INUM.EQ.24) THEN
               WRITE(*,400)ADE1
       FORMAT(//,9X,'THE VALUE FOR ADE1 IS: ',F10.1,' INPUT NEW VALUE'
400
     + ': '$)
               READ(*,70)ADE1
             ELSEIF(INUM.EQ.25) THEN
               WRITE(*,410)ADE2
410
       FORMAT(//,9x,'THE VALUE FOR ADE2 IS: ',F10.1,' INPUT NEW VALUE'
     + ': '$)
              READ(*,70)ADE2
             ELSE
               CHANGE=1
             ENDIF
            ELSE
             CHANGE=1
            END IF
           END DO
           REWIND 1
          ELSEIF(IANSR.EQ.2) THEN
           CALL CLEARSCREEN ( $GCLEARSCREEN )
           CALL DESCRIPT (DSCRPT, SUMFILE, TFILE)
           TP=999.
           AJ=JINC
           Q1 = FLUX(1)
           H1=BL/(AJ-1.0)
C******Initialize depth nodes D(J)
           D(1) = -16.
           DO I=2, JINC
            D(I) = H1*(I-1)*1.E4
            D(I) = ALOG(D(I))
           END DO
            DTJ = TEMPB/(JINC-1)
            DO J=1,JINC
             WATER(J,1) = WATER(J,2)
             CP(J,1) = CP(J,2)
             BK(J,1) = BK(J,2)
             XTIME(J) = 0.
             ZTIME(J) = 0.
             IFLAG(J) = 0.
             JFLAG(J) = 0.
             T(J) = DTJ*(J-1)+TEMPIO
            END DO
             WRITE (4,420) TIME, T(1), T(2), T(3), T(4), T(5), T(6), T(7), T(8)
     + ,T(9),T(10),T(11),T(12)
       FORMAT(13(F9.5,2X))
420
             K=1
             CALL SHOWVALUE (TEMPIO, DENS, FLUX, BL, AK, JINC, TEMPB, ABSORB,
     + BOIL, PL1, PLN1, DE1, PL2, PLN2, DE2, ETIME, ITIME, NXTRA, BLOOD, APL1,
```

```
+ APLN1, ADE1, APL2, APLN2, ADE2, K, XTRA)
             WRITE(3,430)ID, TDELT, NFLX, (I, FLUX(I), I=1, NFLX)
             WRITE(7,430)ID, TDELT, NFLX, (I, FLUX(I), I=1, NFLX)
430
       FORMAT(/,9X,'FLUX FILE I.D.: ',4A2,F7.2,I4://' FLUX(I)='
     + /(' ',10(I5,F8.3)))
             JJJJ=0
             F(1) = -BK(2,1)/(2.0*H1*H1)-BK(1,1)/(2.0*H1*H1)
             G(1) = (BK(1,1)+BK(2,1))/(2.0*H1*H1)+DENS*CP(1,1)/AK
             H(1)=0.0
             ITTR = 0
             IFLX = 1
             EITIM1 = ITIME+1.
             IF (FILNAM.EQ.NOFIL) TDELT=AK
             FFDG = TDELT/AK
             KFDG = FFDG+.0001
             TMPMAX = 0.
             QCONST = ABSORB*60.892
             BLUD = 0.
             M = -1
             TIME = 0.
             ITFLG = 0
             CALL SUB12 (TIME, T, XTIME, JINC, BLUD, CP, BK, NXTRA, XTMP, M, EM)
             DOWHILE (TIME.LT.ITIME.AND.ITFLG.EQ.O.OR.TIME.LT.ETIME)
C******The next program statement automatically chooses the proper
C
        interval in the flux table for the computation of QT and Q1 for
C
        either constant or variable flux.
C
             KFDG (=FFDG) = 1 for constant flux
C
                           = integer ratio of the tabular time step to
C
                             to model the time step for the tabulated flux
               IF (MOD(ITTR,KFDG).EQ.O.AND.IFLX.LT.NFLX) IFLX=IFLX+1
               ITTR = ITTR+1
              P = (ITTR-KFDG*(IFLX-2))/FFDG
              QT = (1.-P)*FLUX(IFLX-1)+P*FLUX(IFLX)
              Q1 = QT*QCONST
              JJJJ = JJJJJ+1
              TIME=JJJJ*AK
              IF (TIME.GE..01.AND.TIME.LE.20.) BLUD=(TIME-AK)/(20.-AK)*
     + BLOOD
              IF(TIME.GE.ETIME) Q1=-5.E-4*(T(1)-23.9)
              Z(1) = -F(1) *T(2) - ((BK(1,1) + BK(2,1)) / (2.0 *H1 *H1) - (DENS*)
     +CP(1,1))/AK)*T(1)+Q1
              N=JINC-1
              DO J=2,N
               F(J) = -BK(J+1,1)/(2.0*H1*H1)
               G(J) = (BK(J,1)+BK(J+1,1))/(2.0*H1*H1)+DENS*CP(J,1)/AK
               H(J) = -BK(J,1)/(2.0*H1*H1)
               Z(J) = -F(J) *T(J+1) - ((BK(J,1)+BK(J+1,1))/(2.*H1*H1)-DENS
     + *CP(J,1)/AK)*T(J)-H(J)*T(J-1)
               IF (J.LE.3) Z(J) = Z(J)-1.675*H1/BK(J,1)*BLUD*(T(J))
     + -TEMPIO+TEMPB)
              END DO
              F(JINC)=0.0
```

```
G(JINC) = (BK(JINC, 1) + BK(JINC-1, 1)) / (2.0*H1*H1) + DENS*
     + CP(JINC, 1)/AK
               H(JINC) = -(BK(JINC, 1) + BK(JINC-1, 1))/(2.0*H1*H1)
               DT=T(JINC-1)-(TEMPIO+TEMPB)
               Z(JINC) = (H(JINC) + (DENS*CP(JINC, 1)/AK))*T(JINC) - H(JINC)*
     + T(JINC-1)-BK(JINC,1)*DT/H1**2
               W(1)=G(1)
               U(1)=Z(1)/W(1)
               DO J=2,JINC
                JM1=J-1
                SV(JM1)=F(JM1)/W(JM1)
                W(J) = G(J) - H(J) *SV(JM1)
                U(J) = (Z(J) - H(J) * U(JM1)) / W(J)
               END DO
                T(JINC)=U(JINC)
                KK=JINC-1
                DO J=1,KK
                 KMJ=JINC-J
                 IF (IFLAG(KMJ).NE.1) THEN
                  T(KMJ)=U(KMJ)-SV(KMJ)*T(KMJ+1)
                  IF (JFLAG(KMJ).NE.1) THEN
                   IF(T(KMJ).GE.BOIL) THEN
                    T(KMJ) = BOIL
                    IF (KMJ.NE.1) THEN
                     Q(KMJ) = BK(KMJ,1)*(T(KMJ)-T(KMJ+1))/H1
                    ELSEIF(KMJ.EQ.1) THEN
                     Q(KMJ) = QT
                    END IF
                    XTIME(KMJ) = 539.*H1/Q(KMJ)*WATER(KMJ,1)
                    ZTIME(KMJ) = XTIME(KMJ) + TIME
                    IFLAG(KMJ) = 1
                   END IF
                  END IF
                 ELSEIF (IFLAG(KMJ).EQ.1) THEN
                  IF (TIME.GE.ZTIME(KMJ)) THEN
                  WATER(KMJ, 1) = PCWATR
                   CP(KMJ, 1) = (CPCON(1)*WATER(KMJ, 1) + CPCON(2)) / (ROCON(1)*
     + WATER(KMJ,1)+ROCON(2))
                   BK(KMJ,1) = (THCON(1)*WATER(KMJ,1)+THCON(2))/(ROCON(1)
     + *WATER(KMJ,1)+ROCON(2))
                   IFLAG(KMJ) = 0
                  XTIME(KMJ) = 0.
                  JFLAG(KMJ) = 1
                 END IF
                ENDIF
               END DO
C******Interpolate extra temperatures between the surface and second node
               IF (NXTRA.NE.O) THEN
                IF (T(2).EQ.T(1)) THEN
C*****For constant temperature
                 DO I=1,NXTRA
                  XTMP(I) = T(2)
```

```
END DO
                ELSEIF (T(2).EQ.T(3)) THEN
C******Linear interpolation
                 DO I=1, NXTRA
                  P = XTRA(I)/D2
                                           !D(1) = 0.
                  XTMP(I) = (1.-P)*T(1)+P*T(2)
                 END DO
                ELSE
C******3-point Lagrange interpolation for equally spaced abscissae
                 DO I=1,NXTRA
                  P = (XTRA(I)-D2)/D2
                                              ID(1) = 0. (SURFACE)
                  XTMP(I) = .5*P*(P-1.)*T(1)+(1.-P**2)*T(2)+.5*P*(P+1.)
     + *T(3)
                 END DO
                END IF
               END IF
               IF (ABS(ETIME-TIME) .LE. O.5*AK) THEN
                DO I=1, JINC
                 IF (IFLAG(I).NE.O) THEN
                  WATER(I,1) = (ZTIME(I)-TIME)/XTIME(I)*(WATER(I,1)-
     + PCWATR) + PCWATR
                  CP(I,1) = (CPCON(1)*WATER(I,1)+CPCON(2))/(ROCON(1)*
     + WATER(I,1)+ROCON(2))
                  BK(I,1) = (THCON(1)*WATER(I,1)+THCON(2))/(ROCON(1)*
    + WATER(I,1)+ROCON(2))
                 END IF
                END DO
                DO I=1,JINC
                 XTIME(I) = 0.
                 IFLAG(I) = 0
                 JFLAG(I) = 1
                END DO
               ENDIF
               IF (T(1).GT.TMPMAX) TMPMAX=T(1)
               ITFLG = -1 !ITFLG SET TO 0 IF ANY TEMPERATURE .GE. 44 DEGREES
               DO J=1,JINC
                IF (T(J).LT.44.) THEN
                 DW(J) = 0.
                ELSE
                 ITFLG = 0
                 IF(T(J).LT.50.) THEN
                  PL1 = PPL1
                  PLN1 = PPLN1
                  DE1 = DDE1
                  APL1 = APPL1
                  APLN1 = APPLN1
                  ADE1 = ADDE1
                  DWLN=PL1+PLN1-DE1/(T(J)+273.)
                  IF(DWLN.GE.87.0) DWLN = 87.0
                  DW(J) = EXP(DWLN)
                 ELSE
                  PL1=PL2
```

```
PLN1=PLN2
             DE1=DE2
             APL1 = APL2
             APLN1 = APLN2
             ADE1 = ADE2
             IF(J.LE.1) THEN
              DWLN = APL1 + APLN1-ADE1/(T(1)+273.)
              IF(DWLN.GE.87.0) DWLN = 87.0
              DW(1) = EXP(DWLN)
             ELSE
              DWLN=PL1+PLN1-DE1/(T(J)+273.)
              IF(DWLN.GE.87.0) DWLN = 87.0
              DW(J) = EXP(DWLN)
             END IF
            END IF
           END IF
          END DO
          IF (JJJJ.LT.2) THEN
           DO I=1,JINC
            SUM(I) = .5*DW(I)
           END DO
          ELSE
           DO I=1,JINC
            IF (SUM(I).LT.(1.0E38)) SUM(I)=SUM(I)+DW(I)
           END DO
          END IF
          IF (NXTRA.NE.O) THEN
           DO J=1, NXTRA
            IF (XTMP(J).LT.44.) THEN
             XDW(J) = 0.
            ELSE
             IF (XTMP(J).LT.50.) THEN
              APL1 = APPL1
              APLN1 = APPLN1
              ADE1 = ADDE1
             ELSE
              APL1 = APL2
              APLN1 = APLN2
              ADE1 = ADE2
             END IF
             IF (TP.EQ.999..AND.XTMP(4).GE.45.)
+ TP=TIME
             DWLN = APL1+APLN1-ADE1/(XTMP(J)+273.)
             IF(DWLN.GE.87.0) DWLN=87.0
             XDW(J) = EXP(DWLN)
            END IF
           END DO
           IF (JJJJ.LT.2) THEN
            DO J=1,NXTRA
             XSUM(J) = 0.5*XDW(J)
           END DO
           ELSE
```

```
DO J=1,NXTRA
                   IF (XSUM(J).LT.1.0E38) XSUM(J)=XSUM(J)+XDW(J)
                 END DO
                END IF
               END IF
                EMTIME = AINT(1000.*(TIME+.00001))/100.
                IF(TIME.LT.10..AND.AMOD(EMTIME,1.).EQ.O..OR.TIME.GE.10.
     + .AND.AMOD(EMTIME, 10.).EQ.O.) THEN
                WRITE (4,420) TIME, T(1), T(2), T(3), T(4), T(5), T(6), T(7),
     + T(8),T(9),T(10),T(11),T(12)
                PTS=PTS+1
               ENDIF
                IF (ITFLG.NE.O.AND.TIME.GE.ETIME.OR.JJJJ.EQ.M*100.OR.JJJJ
     + .EQ.1) CALL SUB12(TIME, T, XTIME, JINC, BLUD, CP, BK, NXTRA, XTMP, M, EM)
             END DO
             REWIND (4)
             CLOSE (4)
             DO I=1,JINC
              W(I) = (SUM(I) - .5*DW(I))*AK
             END DO
             IF (NXTRA.NE.O) THEN
              DO J=1,NXTRA
               XW(J) = (XSUM(J) - .5*XDW(J))*AK
              END DO
             END IF
C^{*******Select W(J)} and D(J) near W(J) = 1
470
             NN = 3
             J=1
             DOWHILE (J.LE.JINC)
              JLT1 = J
              IF(W(J).GT.1.) THEN
               IF (J.EQ.JINC) THEN
                NN=2
                WRITE(3,440)(W(K),K=JLT1-1,JLT1+1)
                WRITE(7, 440)(W(K), K=JLT1-1, JLT1+1)
440
       FORMAT(/(1X,'W=',E20.5))
                WRITE(3,450)(D(K),K=JLT1-1,JLT1+1)
                WRITE(7,450)(D(K),K=JLT1-1,JLT1+1)
450
       FORMAT(/(1X,'D=',E20.5))
               END IF
               J=J+1
              ELSEIF(W(J).EQ.1.) THEN
               MN=1
               J=JINC+1
              ELSEIF(W(J).LT.1.) THEN
               IF (J.EQ.1) JLT1=2
               IF (J.EQ.JINC) JLT1=JINC-1
               WRITE(3,440)(W(K),K=JLT1-1,JLT1+1)
               WRITE(7,440)(W(K),K=JLT1-1,JLT1+1)
               WRITE(3,450)(D(K),K=JLT1-1,JLT1+1)
               WRITE(7,450)(D(K),K=JLT1-1,JLT1+1)
               IF (NXTRAO.NE.O.AND.JLT1.LE.2) THEN
```

```
WRITE(*,460)
460
       FORMAT(/,9x,'W=1 LIES ABOVE NODE 2. INTERCOLLATING VALUES OF D'/
     + ,9x,'AND W COMPUTED FROM INTERPOLATED VALUES OF D AND',/,9x,
     + 'TEMPERATURE. ',/)
                 WRITE(3,460)
                 WRITE (7,460)
                 WRITE(1)D(1)
                 WRITE(2)W(1)
                 DO J=1,NXTRA
                  WRITE(1)XTRALG(J)
                  WRITE(2)XW(J)
                 END DO
                 DO J=2, JINC
                  WRITE(1)D(J)
                 WRITE(2)W(J)
                 END DO
                 REWIND 1
                 REWIND 2
                 DO J=1,JINC
                 READ(1)D(J)
                 READ(2)W(J)
                 END DO
                 REWIND 1
                 REWIND 2
                 NXTRAO = 0
                 GO TO 470
               END IF
               J=JINC+1
              END IF
             END DO
         IF (MN.EQ.O) THEN
          NXTRAO = NXTRA
          IF (W(JLT1+1).EQ.O..AND.NN.EQ.3) NN=2
          IF(W(JLT1-1).LT.1.0)THEN
            TD=0.0
            IERR=0
          ELSE
            CALL DEPTH(D(JLT1-1), W(JLT1-1), NN, TD, IERR)
C******If Lagrangian interpolation didn't work, use linear interpolation
            IF(NN.EQ.3) THEN
              IF(W(JLT1-1).GE.1.0.AND.W(JLT1).LE.1.0.AND.(D(JLT1-1).
             GT.TD.OR.D(JLT1).LT.TD)) THEN
                NN=2
                CALL DEPTH(D(JLT1-1), W(JLT1-1), NN, TD, IERR)
              ELSEIF (W(JLT1).GE.1.0.AND.W(JLT1+1).LE.1.0.AND.
             (D(JLT1).GT.TD.OR.D(JLT1+1).LT.TD)) THEN
                JLT1=JLT1+1
                CALL DEPTH(D(JLT1-1), W(JLT1-1), NN, TD, IERR)
              ENDIF
            ENDIF
          ENDIF
```

```
IF (IERR.NE.O) THEN
            WRITE(*,480)
            WRITE(3,480)
            WRITE(7,480)
480
        FORMAT(9X, 'ERROR IN SUBROUTINE "DEPTH". EXITING.'/)
            CALL ANOTHER (AGAIN)
           ENDIF
           IF (NN.EQ.2.AND.JLT1.EQ.JINC) THEN
            WRITE(3,490)MAXDIM
            WRITE (7,490) MAXDIM
490
       FORMAT(/1X, 'THE MODEL BLEW UP: DAMAGE > 1 AT NODE ', 12/)
            CALL SUB1020 (W, JINC, D, TMPMAX, TD, TIME, TP)
            CALL SUB1020 (W, JINC, D, TMPMAX, TD, TIME, TP)
           ENDIF
         ELSE
           TD=EXP(D(J))
           CALL SUB1020 (W, JINC, D, TMPMAX, TD, TIME, TP)
         END IF
          CALL HARVARD (PROFILE, TFILE, SUMFILE, PTS)
        END IF
       ELSEIF(PROCED.EQ.1) THEN
        IF (AGAIN.EQ.O) THEN
          CALL SHOWVALUE (TEMPIO, DENS, FLUX, BL, AK, JINC, TEMPB,
         ABSORB, BOIL, PL1, PLN1, DE1, PL2, PLN2, DE2, ETIME, ITIME, NXTRA,
          BLOOD, APL1, APLN1, ADE1, APL2, APLN2, ADE2, K, XTRA)
        ENDIF
       ENDIF
      END DO
      CLOSE(1)
      CLOSE(2)
      CLOSE(3)
      CLOSE (4)
      CLOSE(7)
      CALL COLORS
      DUMMY2=SETVIDEOMODE( $DEFAULTMODE )
      STOP
      END
      SUBROUTINE COLORS
         INCLUDE 'FGRAPH.FD'
         INTEGER*2 LOOP, LOOP1, DUMMY2
         REAL RND1, RND2
         DUMMY2=SETVIDEOMODE( $MRES256COLOR )
         DO LOOP1=1,10
         WRITE(*,10)
10
       FORMAT(///,10X,'BURNSIM',///,15X,'BURNSIM',///,20X,'BURNSIM')
         DUMMY2=SETCOLOR(MOD( getcolor()+1, 16)) ! Set next color
          DO loop=1,3200
C*****Set a random pixel, normalized to be on the screen
           CALL RANDOM ( RND1 )
```

```
CALL RANDOM ( RND2 )
           DUMMY2=SETPIXEL( INT2( RND1*320 ), INT2( RND2*200 ) )
          END DO
         END DO
         DUMMY2=SETVIDEOMODE( $MAXRESMODE )
      SUBROUTINE WELCOME (PROFILE)
         CHARACTER PROFILE*8
         CALL CLEARSCREEN ( $GCLEARSCREEN )
         WRITE(*,10)
10
       FORMAT(//,9X,'WELCOME TO BURNSIM. TO BEGIN RUNNING THE PROGRAM,',
     + ' BURNSIM', /, 9X, 'FIRST NEEDS TO KNOW THE NAME OF THE FILE THAT',
     + ' YOU WANT TO', /, 9X, 'STORE THE OUTPUT DATA IN. THIS FILE WILL',
     + ' CONTAIN ALL OF THE', /, 9X, 'INPUT PARAMETERS AS WELL AS THE',
     + ' OUTPUT FOR EACH ITERATION THE', /, 9X, 'MODEL PERFORMS. THIS',
     + ' FILE CAN BE CALLED ANYTHING UP TO EIGHT', /, 9X, 'CHARACTERS',
     + 'LONG.',//,15X,'PLEASE ENTER A NAME FOR THE OUTPUT FILE: '$)
         READ(*,20)PROFILE
       FORMAT (A8)
C******Set up parameters for this run
         CALL CLEARSCREEN ( $GCLEARSCREEN )
         WRITE(*,30)
30
       FORMAT(///,9x,'NEXT BURNSIM WILL SHOW YOU THE PRESENT INPUT',
     + ' PARAMETERS.',/,9X,'UNDER THE LIST OF PARAMETERS YOU WILL SEE A'
     + ,' QUESTION ASKING',/,9X,'IF YOU WISH TO CONTINUE. IF YOU WANT',
     + ' TO EXIT THE PROGRAM AT ',/,9X,'THAT POINT, TYPE N. OTHERWISE',
     + ' TYPE Y.',///,9X,'TO CONTINUE ON TO THE LIST OF INPUT',
     + ' PARAMETERS TYPE A <CR>.')
         READ(*,*)
         END
      SUBROUTINE READDATA (TEMPIO, DENS, QO, BL, AK, BOIL, ABSORB, JINC,
     + TEMPB, ITIME, ETIME, PCWATR, BLOOD, CP, BK, PL2, PLN2, PL1, PLN1, DE2,
     + DE1, APL1, APLN1, APL2, APLN2, ADE1, ADE2, WATER)
         REAL ITIME
         DIMENSION CP(12,2), BK(12,2), WATER(12,2)
         OPEN(UNIT=1,FILE='REN12.DAT',FORM='FORMATTED',STATUS='OLD')
         READ(1,10)TEMPIO,DENS,QO,BL,AK,BOIL,ABSORB
10
       FORMAT(7F10.5)
         READ(1,20)JINC, TEMPB, ITIME, ETIME, PCWATR, BLOOD
20
       FORMAT(1110,5F10.5)
         READ(1,30)(CP(J,2),J=1,JINC)
30
       FORMAT (6F10.5)
         READ(1,30)(BK(J,2),J=1,JINC)
         READ(1,30)PL2,PLN2,PL1,PLN1,DE2,DE1
         READ(1,30)APL1,APLN1,APL2,APLN2,ADE1,ADE2
         READ(1,30,END=40)(WATER(I,2),I=1,JINC)
40
         CLOSE(1)
         CALL CLEARSCREEN ( $GCLEARSCREEN )
         END
```

```
SUBROUTINE SHOWVALUE (TEMPIO, DENS, FLUX, BL, AK, JINC, TEMPB,
      + ABSORB, BOIL, PL1, PLN1, DE1, PL2, PLN2, DE2, ETIME, ITIME,
      + NXTRA, BLOOD, APL1, APLN1, ADE1, APL2, APLN2, ADE2, K, XTRA)
          REAL ITIME
          DIMENSION FLUX(600), XTRA(8)
          CALL CLEARSCREEN ( $GCLEARSCREEN )
          IF(K.NE.1) THEN
           WRITE (*,10)
10
       FORMAT(///,30X,'SKIN DIFFUSION DATA'/,30X,'INPUT PARAMETER LIST')
           WRITE(*,20)TEMPIO,DENS,FLUX(1),BL,AK,JINC,TEMPB,ABSORB,BOIL
20
       FORMAT(/, 4X, 'TEMPIO = ',F10.5,6X, 'DENS = ',F10.5,7X,'Q1 = ',
     + F10.5,/,4X,'BL = ',F10.5,10X,'AK = ',F10.5,9X,'JINC = ',I2,/,4X,'
     + 'TEMPB = ',F10.5,7X,'ABSORB = ',F10.5,5X,'BOIL = ',F10.5,/)
           WRITE (*,30)PL1,PLN1,DE1,PL2,PLN2,DE2,ETIME,ITIME,NXTRA,BLOOD
30
       FORMAT(4X, 'PL1 = ',F10.5,9X, 'PLN1 = ',F10.5,7X, 'DE1 = ',F10.1,/,
     + 4X, 'PL2 = ',F10.5,9X, 'PLN2 = ',F10.5,7X, 'DE2 = ',F10.1,/,4X,
     + 'ETIME = ',F10.5,7X,'ITIME = ',F10.5,6X,'NXTRA = ',I2,/,4X,
     + 'BLOOD = ',F10.5,/)
          WRITE(*, 40) APL1, APLN1, ADE1, APL2, APLN2, ADE2
40
       FORMAT(4X, 'APL1 = ',F10.5,8X, 'APLN1 = ',F10.5,6X, 'ADE1 = ',F10.1,
     + /,4X,'APL2 = ',F10.5,8X,'APLN2 = 'F10.5,6X,'ADE2 = ',F10.1,/)
          IF (NXTRA.GT.0) WRITE(*,50) (XTRA(I),I=1,NXTRA)
       FORMAT(5X, 'THE EXTRA NODES ARE: ',8F6.1)
50
         ELSE
          WRITE (3, 10)
          WRITE (7, 10)
          WRITE(3,20)TEMPIO,DENS,FLUX(1),BL,AK,JINC,TEMPB,ABSORB,BOIL
          WRITE(7,20)TEMPIO,DENS,FLUX(1),BL,AK,JINC,TEMPB,ABSORB,BOIL
          WRITE (3,30)PL1,PLN1,DE1,PL2,PLN2,DE2,ETIME,ITIME,NXTRA,BLOOD
          WRITE (7,30)PL1,PLN1,DE1,PL2,PLN2,DE2,ETIME,ITIME,NXTRA,BLOOD
          WRITE(3,40)APL1,APLN1,ADE1,APL2,APLN2,ADE2
          WRITE(7,40)APL1,APLN1,ADE1,APL2,APLN2,ADE2
          IF (NXTRA.GT.0) WRITE (3,50) (XTRA(I), I=1, NXTRA)
          IF (NXTRA.GT.0) WRITE(7,50) (XTRA(I),I=1,NXTRA)
          K=0
         ENDIF
         END
      SUBROUTINE PROCEED (RESP, PROCED, AGAIN)
         CHARACTER RESP*1
         INTEGER PROCED, AGAIN
         WRITE(*,10)
10
       FORMAT(//,15X,'DO YOU WISH TO CONTINUE? TYPE Y OR N '$)
         READ(*,20)RESP
20
       FORMAT(A1)
         IF (RESP.EQ.'Y'.OR.RESP.EQ.'y') THEN
          PROCED=0
         ELSE
          PROCED=1
          CALL ANOTHER (AGAIN)
         ENDIF
         END
```

```
SUBROUTINE ANOTHER (AGAIN)
          CHARACTER RESP*1
          INTEGER AGAIN
          WRITE(*,10)
10
        FORMAT(//,15X,'DO YOU WANT TO DO ANOTHER RUN? TYPE Y OR N '$)
          READ(*,20)RESP
        FORMAT(A1)
20
          IF(RESP.EQ.'Y'.OR.RESP.EQ.'y') THEN
          ELSE
           AGAIN=1
          END IF
          END
       SUBROUTINE DESCRIPT (DSCRPT, SUMFILE, TFILE)
          CHARACTER SUMFILE*8, TFILE*8
          DIMENSION DSCRPT(20)
          WRITE(*,10)
10
       FORMAT(///,9X,'ENTER THE MODEL NAME OR DESCRIPTION (UP TO 80',
     + /,9X,'CHARACTERS). THIS INFORMATION WILL BE USED',/,9X,
     + 'AS A TITLE ON THE SUMMARY PAGE. '$)
         READ(*,20)DSCRPT
20
       FORMAT (20A4)
         WRITE(3,30)DSCRPT
30
       FORMAT(//,10X,'MODEL NAME OR DESCRIPTION: ',20A4)
         CALL CLEARSCREEN ( $GCLEARSCREEN )
         WRITE(*,40)
40
       FORMAT (///, 9X, 'NOW ENTER THE SUMMARY FILENAME (UP TO 8',
     + /,9X, 'CHARACTERS). THIS FILE WILL CONTAIN A',/,9X, 'SUMMARY'
     + ' OF THE SIMULATION. '$)
         READ(*,50)SUMFILE
50
       FORMAT(A8)
         OPEN (UNIT=7, FILE=SUMFILE, FORM='FORMATTED', STATUS='UNKNOWN')
         WRITE (7,30) DSCRPT
         CALL CLEARSCREEN ( $GCLEARSCREEN )
         WRITE(*,60)
       FORMAT(///,9X,'NOW ENTER THE TEMPERATURE FILE (UP TO 8',
60
     + ' CHARACTERS).',/,9X,'THIS FILE WILL CONTAIN A LIST OF THE',
     + ' TEMPERATURES', /, 9X, 'AT THE VARIOUS NODES DURING THE SIMULATION'
     + '. '$)
         READ(*,70)TFILE
70
       FORMAT (A8)
         OPEN(UNIT=4,FILE=TFILE,FORM='FORMATTED',STATUS='UNKNOWN')
      SUBROUTINE SUB12(TIME, T, XTIME, JINC, BLUD, CP, BK, NXTRA, XTMP, M, EM)
         DIMENSION T(12), XTIME(12), CP(12,2), BK(12,2), XTMP(8)
         WRITE(3,10)TIME
         WRITE (*,10) TIME, (T(I), XTIME(I), I=1, JINC)
10
       FORMAT(/,45X,5HTIME=,F10.6:,T4,'T=',6X,'XTIME='/('',2G12.4))
         WRITE(*,20)BLUD
20
       FORMAT(1X,'BLUD = ',F6.5)
```

```
WRITE(3,30)(XTIME(I),I=1,JINC)
       FORMAT(2X,'XTIME=',F10.5)
30
         WRITE(3,40)T(1),CP(1,1),BK(1,1)
40
       FORMAT(2X, 'T=', G16.5:, 2X, 'CP=', G16.5, 2X, 'BK=', G16.5)
         IF (NXTRA.NE.O) THEN
          DO J=1, NXTRA
           WRITE(3,40)XTMP(J)
          END DO
         END IF
         WRITE(3,40)(T(J),CP(J,1),BK(J,1),J=2,JINC)
         EM = M
         END
      SUBROUTINE DEPTH(X,Y,N,TD,IERR)
C******Inverse interpolation on two or three points to determine
        threshold depth (predicted burn depth) using either Y or LOG(Y)
         DIMENSION X(1),Y(1),Z(3)
         IERR = 0
         IF (N.LT.2) IERR=-1
         IF(IERR.NE.-1) THEN
          DO 100 I=1,N
100
          Z(I) = Y(I)
          z_0 = 1.
          IF (Z(1).NE.O..AND.Z(2).NE.O.) THEN
                                                    !USE LOGARITHMS?
           IF (N.EQ.3.AND.Z(3).EQ.0.) N=2
           zo = o.
                            !USE LOGARITHMS
           DO 120 I=1,N
120
            Z(I) = ALOG(Z(I))
          END IF
140
          HO = Z(2)-Z(1)
          IF (HO.EQ.O.) IERR=-1
          IF (N.NE.2.AND.IERR.NE.-1) THEN
           H1 = Z(3) - Z(2)
           IF (H1.EQ.O.) IERR=-1
           IF(IERR.NE.-1) H2 = Z(3)-Z(1)
           IF (H2.EQ.O.) IERR=-1
           IF(IERR.NE.-1) DZ3 = ZO-Z(3)
          END IF
          IF(IERR.NE.-1) THEN
160
           DZ2 = ZO-Z(2)
           DZ1 = Z0-Z(1)
           IF (N.NE.2) THEN
            TD = DZ1*DZ2*X(3)/(H1*H2)-DZ1*X(2)*DZ3/(H0*H1)+X(1)*DZ2*DZ3
     +/(H0*H2)
           ELSEIF(N.EQ.2) THEN
180
            TD = (DZ1*X(2)-X(1)*DZ2)/H0
           END IF
200
           TD = EXP(TD)
          END IF
         END IF
         END
```

```
SUBROUTINE SUB1020(W, JINC, D, TMPMAX, TD, TIME, TP)
         DIMENSION W(12),D(12)
         WRITE(3,10)(W(I),I=1,JINC)
10
       FORMAT(/(1X,'W=',E20.5))
         WRITE(7,20)(W(I),EXP(D(I)),I=1,JINC)
       FORMAT(/(1X,'W =',E20.5,5X,'AT DEPTH (IN MICRONS)=',G20.6))
20
         WRITE(3,30)TMPMAX
         WRITE (7,30) TMPMAX
         WRITE(*,30)TMPMAX
30
       FORMAT(/,1x,'MAXIMUM TEMPERATURE = ',F8.3)
         WRITE(*,40)TD
         WRITE (3,40) TD
         WRITE (7,40) TD
40
       FORMAT(/,1X,'THRESHOLD DEPTH = ',G20.4)
         WRITE(3,50)TIME
         WRITE (7,50) TIME
         WRITE (*,50) TIME
50
       FORMAT(/,1X,'FINAL\ TIME = ',F7.2)
         IF(TP.NE.999.) THEN
          WRITE(3,60)TP
          WRITE (7,60) TP
          WRITE(*,60)TP
       FORMAT(/,1X,'TIME TO PAIN IS ',F7.2,' SECONDS.')
60
         END IF
         END
      SUBROUTINE HARVARD (PROFILE, TFILE, SUMFILE, PTS)
         CHARACTER PROFILE*8, SUMFILE*8, TFILE*8, HGPLOT*1, HG*12
         INTEGER PTS
         WRITE(*,10)
10
       FORMAT(///,9X,'TYPE A <CR> TO CONTINUE.')
         READ(*,*)
         CALL CLEARSCREEN ( $GCLEARSCREEN )
         WRITE(*,20)
20
       FORMAT(///,9X,'DO YOU WANT TO PLOT THE TEMPERATURES VS. TIME',/,
     + 9X, 'TIME IN HARVARD GRAPHICS? TYPE Y/N '$)
         READ(*,30) HGPLOT
30
       FORMAT(A1)
         IF (HGPLOT .EQ. 'Y' .OR. HGPLOT .EQ. 'y') THEN
          CALL PLOTHG(PTS, TFILE, HG)
         ENDIF
         CALL CLEARSCREEN ( $GCLEARSCREEN )
         WRITE(*,40)PROFILE,TFILE
40
       FORMAT(//,9X,'THE MODEL OUTPUT IS FOUND IN FILE: ',A10,/,9X,
     + 'USE "PRINT" OR "TYPE" AFTER YOU EXIT THE PROGRAM TO SEE IT.',
     + //,9x,'THE TEMPERATURES AT EACH NODE ARE IN FILE: ',A10,/,9x,
     + 'USE "PRINT" OR "TYPE" AFTER YOU EXIT THE PROGRAM TO SEE IT.')
         IF (HGPLOT .EQ. 'Y' .OR. HGPLOT .EQ. 'y') THEN
          WRITE(*,50)HG
50
       FORMAT(//,9X,'THE TEMPERATURES FOR THE HARVARD GRAPHICS PLOT',
     + 'ARE IN FILE: ',/,9X,A12,'. USE "PRINT" OR "TYPE" AFTER YOU',
     + ' EXIT THE PROGRAM', /, 9X, 'TO SEE IT.')
```

```
ENDIF
         WRITE(*,60)SUMFILE
       FORMAT(//,9X,'THE SUMMARY PRINTOUT IS IN FILE: ',A10,/,9X,'USE',
60
     + ' "PRINT" OR "TYPE" AFTER YOU EXIT THE PROGRAM TO SEE IT.',///,
     + 12X, 'TYPE A <CR> TO CONTINUE.')
         READ(*,*)
         CALL CLEARSCREEN ( $GCLEARSCREEN )
      SUBROUTINE PLOTHG(PTS, TPFILE, HG)
         REAL TIME(800), T1(800), T2(800), T3(800), T4(800), T5(800),
     + T6(800), T7(800), T8(800), T9(800), T10(800), T11(800), T12(800)
         INTEGER PTS
         CHARACTER HG*12, TPFILE*8
         OPEN (UNIT=4, FILE=TPFILE, FORM='FORMATTED', STATUS='UNKNOWN')
         DO I=1,PTS
          READ (4,40) TIME (I), T1(I), T2(I), T3(I), T4(I), T5(I)
     + ,T6(I),T7(I),T8(I),T9(I),T10(I),T11(I),T12(I)
40
       FORMAT(13(F9.5,2X))
         END DO
         WRITE(*,10)TPFILE
         CLOSE (4)
10
       FORMAT(/,9X,'THE TEMPERATURE DATA IS STORED IN FILE: ',A8)
         WRITE(*,20)
20
       FORMAT(/,9X,'ENTER THE FILE TO STORE HARVARD GRAPHICS ',/,
     + 9X, 'TEMPERATURES USING UP TO 12 CHARACTERS', /, 9X, 'INCLUDING'
     + 'THE ENDING .DAT ',$)
         READ(*,30) HG
30
       FORMAT (A12)
         IF(PTS.LE.60) THEN
          OPEN(UNIT=5, FILE=HG, FORM='FORMATTED', STATUS='UNKNOWN')
          DO J=1,PTS
           WRITE(5,60) TIME(J), T1(J), T2(J), T3(J), T4(J), T5(J),
     + T6(J), T7(J), T8(J), T9(J), T10(J), T11(J), T12(J)
60
       FORMAT(13(F9.5,2X))
          END DO
          CLOSE (5)
         ELSE
          INTERVAL=INT(PTS/60)
          OPEN(UNIT=5, FILE=HG, FORM='FORMATTED', STATUS='UNKNOWN')
          DO J=1, PTS, INTERVAL
           WRITE(5,80) TIME(J),T1(J),T2(J),T3(J),T4(J),T5(J),
     + T6(J), T7(J), T8(J), T9(J), T10(J), T11(J), T12(J)
80
       FORMAT(13(F9.5,2X))
          END DO
          CLOSE (5)
         END IF
         END
```

APPENDIX C

REN12.DAT

This next file contains the initial values of the variables and constants required by BURNSIM. The file is REN12.DAT.

```
32.5,1.,3.54,0.22,0.01,100.15,0.613
12,4.5,80.,3.02,0.137,0.001
.5139,.8513,.8678,.8681,.8561,.8349,.8086
.7802,.7537,.7326,.7209,.7209
.00059604,.0012236,.0012541,.0012547,.0012322,.0011931,.0011439
.0010912,.0010419,.0010028,.0009810,.0008
2.24,239.47,1.46,147.37,80000.,50000.
.78,285.52,.60,117.43,93534.9,39109.8
.137,.72596,.75574,.75638,.73439,.69632,.64869
.598,.55081,.51364,.49298,.3
```

See the users manual for definitions of these abbreviations (eg. TEMPIO).

DOM 1	DOM 2	DOW 3
<u>ROW 1</u>	<u>ROW 2</u>	ROW 3
TEMPIO = 32.5	JINC = 12	Cp(1) = .5139
DENS = 1.	TEMPB = 4.5	Cp(2) = .8513
Q0 = 3.54		Cp(3) = .8678
BL = 0.22	ETIME = 3.02	Cp(4) = .8561
AK = 0.01	PCWATER = 0.137	
BOIL = 100.15	BLOOD = 0.001	Cp(6) = .8349
ASORB = 0.613		Cp(7) = .8086
ROW 4	<u>ROW 5</u>	ROW 6
Cp(8) = .7802	BK(1) = .00059604	BK(8) = .0010912
Cp(9) = .7537	BK(2) = .0012236	BK(9) = .0010419
Cp(10) = .7326	BK(3) = .0012541	BK(10) = .0010028
Cp(11) = .7209	BK(4) = .0012547	BK(11) = .0009810
Cp(12) = .7209	BK(5) = .0012322	BK(12) = .0008
	BK(6) = .0011931	•
	BK(7) = .0011439	
ROW 7	ROW 8	ROW 9
PL2 = 2.24	APL1 = .78	WATER(1) = .137
PLN2 = 239.47	APLN1 = 285.52	WATER(2) = .72596
PL1 = 1.46	APL2 = .60	WATER(3) = .75574
PLN1 = 147.37	APLN2 = 117.43	WATER(4) = .75638
DE2 = 80000.	ADE1 = 93534.9	WATER(5) = .73439
DE1 = 50000.	ADE2 = 39109.8	WATER(6) = .69632
		WATER(7) = .64869

ROW 10

WATER(8) = .598 WATER(9) = .55081 WATER(10) = .51364 WATER(11) = .49298 WATER(12) = .3

Initial distribution

Commander, U.S. Army Natick Research,
Development and Engineering Center
ATTN: SATNC-MIL (Documents
Librarian)
Natick, MA 01760-5040

U.S. Army Communications-Electronics Command ATTN: AMSEL-RD-ESA-D Fort Monmouth, NJ 07703

Commander/Director
U.S. Army Combat Surveillance
and Target Acquisition Lab
ATTN: DELCS-D
Fort Monmouth, NJ 07703-5304

Commander
10th Medical Laboratory
ATTN: Audiologist
APO New York 09180

Naval Air Development Center Technical Information Division Technical Support Detachment Warminster, PA 18974

Commanding Officer, Naval Medical Research and Development Command National Naval Medical Center Bethesda, MD 20814-5044

Deputy Director, Defense Research and Engineering ATTN: Military Assistant for Medical and Life Sciences Washington, DC 20301-3080

Commander, U.S. Army Research Institute of Environmental Medicine Natick, MA 01760 Library Naval Submarine Medical Research Lab Box 900, Naval Sub Base Groton, CT 06349-5900

Director, U.S. Army Human Engineering Laboratory ATTN: Technical Library Aberdeen Proving Ground, MD 21005

Commander
Man-Machine Integration System
Code 602
Naval Air Development Center
Warminster, PA 18974

Commander Naval Air Development Center ATTN: Code 602-B (Mr. Brindle) Warminster, PA 18974

Commanding Officer Armstrong Laboratory Wright-Patterson Air Force Base, OH 45433-6573

Director Army Audiology and Speech Center Walter Reed Army Medical Center Washington, DC 20307-5001

Commander, U.S. Army Institute of Dental Research ATTN: Jean A. Setterstrom, Ph. D. Walter Reed Army Medical Center Washington, DC 20307-5300

Commander, U.S. Army Test and Evaluation Command ATTN: AMSTE-AD-H Aberdeen Proving Ground, MD 21005 Naval Air Systems Command Technical Air Library 950D Room 278, Jefferson Plaza II Department of the Navy Washington, DC 20361

Director
U.S. Army Ballistic
Research Laboratory
ATTN: DRXBR-OD-ST Tech Reports
Aberdeen Proving Ground, MD 21005

Commander
U.S. Army Medical Research
Institute of Chemical Defense
ATTN: SGRD-UV-AO
Aberdeen Proving Ground,
MD 21010-5425

Commander, U.S. Army Medical Research and Development Command ATTN: SGRD-RMS (Ms. Madigan) Fort Detrick, Frederick, MD 21702-5012

Director Walter Reed Army Institute of Research Washington, DC 20307-5100

HQ DA (DASG-PSP-O) 5109 Leesburg Pike Falls Church, VA 22041-3258

Harry Diamond Laboratories ATTN: Technical Information Branch 2800 Powder Mill Road Adelphi, MD 20783-1197

U.S. Army Materiel Systems
Analysis Agency
ATTN: AMXSY-PA (Reports Processing)
Aberdeen Proving Ground
MD 21005-5071

U.S. Army Ordnance Center and School LibrarySimpson Hall, Building 3071Aberdeen Proving Ground, MD 21005

U.S. Army Environmental
Hygiene Agency
Building E2100
Aberdeen Proving Ground, MD 21010

Technical Library Chemical Research and Development Center Aberdeen Proving Ground, MD 21010--5423

Commander
U.S. Army Medical Research
Institute of Infectious Disease
SGRD-UIZ-C
Fort Detrick, Frederick, MD 21702

Director, Biological Sciences Division Office of Naval Research 600 North Quincy Street Arlington, VA 22217

Commander
U.S. Army Materiel Command
ATTN: AMCDE-XS
5001 Eisenhower Avenue
Alexandria, VA 22333

Commandant
U.S. Army Aviation
Logistics School ATTN: ATSQ-TDN
Fort Eustis, VA 23604

Headquarters (ATMD)
U.S. Army Training
and Doctrine Command
ATTN: ATBO-M
Fort Monroe, VA 23651

Structures Laboratory Library USARTL-AVSCOM NASA Langley Research Center Mail Stop 266 Hampton, VA 23665

Naval Aerospace Medical Institute Library Building 1953, Code 03L Pensacola, FL 32508-5600

Command Surgeon HQ USCENTCOM (CCSG) U.S. Central Command MacDill Air Force Base FL 33608

Air University Library
(AUL/LSE)
Maxwell Air Fore Base, AL 36112

U.S. Air Force Institute of Technology (AFIT/LDEE) Building 640, Area B Wright-Patterson Air Force Base, OH 45433

Henry L. Taylor Director, Institute of Aviation University of Illinois-Willard Airport Savoy, IL 61874

Chief, National Guard Bureau ATTN: NGB-ARS (COL Urbauer) Room 410, Park Center 4 4501 Ford Avenue Alexandria, VA 22302-1451

Commander
U.S. Army Aviation Systems Command
ATTN: SGRD-UAX-AL (LTC Gillette)
4300 Goodfellow Blvd., Building 105
St. Louis, MO 63120

U.S. Army Aviation Systems Command Library and Information Center Branch ATTN: AMSAV-DIL4300 Goodfellow BoulevardSt. Louis, MO 63120

Federal Aviation Administration Civil Aeromedical Institute Library AAM-400A P.O. Box 25082 Oklahoma City, OK 73125

Commander
U.S. Army Academy
of Health Sciences
ATTN: Library
Fort Sam Houston, TX 78234

Commander
U.S. Army Institute of Surgical Research
ATTN: SGRD-USM (Jan Duke)
Fort Sam Houston, TX 78234-6200

AAMRL/HEX Wright-Patterson Air Force Base, OH 45433

John A. Dellinger, Southwest Research Institute P. 0. Box 28510 San Antonio, TX 78284

Product Manager Aviation Life Support Equipment ATTN: AMCPM-ALSE 4300 Goodfellow Boulevard St. Louis, MO 63120-1798

Commander
U.S. Army Aviation
Systems Command
ATTN: AMSAV-ED
4300 Goodfellow Boulevard
St. Louis, MO 63120

Commanding Officer Naval Biodynamics Laboratory P.O. Box 24907 New Orleans, LA 70189-0407

Assistant Commandant U.S. Army Field Artillery School ATTN: Morris Swott Technical Library Fort Sill, OK 73503-0312

Commander
U.S. Army Health Services Command
ATTN: HSOP-SO
Fort Sam Houston, TX 78234-6000

U.S. Army Dugway Proving Ground Technical Library, Building 5330 Dugway, UT 84022

U.S. Army Yuma Proving Ground Technical Library Yuma, AZ 85364

AFFTC Technical Library 6510 TW/TSTL Edwards Air Force Base, CA 93523-5000

Commander Code 3431 Naval Weapons Center China Lake, CA 93555

Aeromechanics Laboratory U.S. Army Research and Technical Labs Ames Research Center, M/S 215-1 Moffett Field, CA 94035

Sixth U.S. Army ATTN: SMA Presidio of San Francisco, CA 94129 Commander
U.S. Army Aeromedical Center
Fort Rucker, AL 36362

U.S. Air Force School
of Aerospace Medicine
Strughold Aeromedical Library Technical
Reports Section (TSKD)
Brooks Air Force Base, TX 78235-5301

Dr. Diane Damos Department of Human Factors ISSM, USC Los Angeles, CA 90089-0021

U.S. Army White Sands
Missile Range
ATTN: STEWS-IM-ST
White Sands Missile Range, NM 88002

U.S. Army Aviation Engineering
Flight Activity
ATTN: SAVTE-M (Tech Lib) Stop 217
Edwards Air Force Base, CA 93523-5000

Ms. Sandra G. Hart Ames Research Center MS 262-3 Moffett Field, CA 94035

Commander, Letterman Army Institute of Research ATTN: Medical Research Library Presidio of San Francisco, CA 94129

Commander
U.S. Army Medical Materiel
Development Activity
Fort Detrick, Frederick, MD 21702-5009

Commander
U.S. Army Aviation Center
Directorate of Combat Developments
Building 507
Fort Rucker, AL 36362

U. S. Army Research Institute Aviation R&D Activity ATTN: PERI-IR Fort Rucker, AL 36362

Commander U.S. Army Safety Center Fort Rucker, AL 36362

U.S. Army Aircraft Development Test Activity ATTN: STEBG-MP-P Cairns Army Air Field Fort Rucker, AL 36362

Commander U.S. Army Medical Research and Development Command ATTN: SGRD-PLC (COL Schnakenberg) Fort Detrick, Frederick, MD 21702

MAJ John Wilson TRADOC Aviation LO Embassy of the United States APO New York 09777

Netherlands Army Liaison Office Building 602 Fort Rucker, AL 36362

British Army Liaison Office Building 602 Fort Rucker, AL 36362

Italian Army Liaison Office Building 602 Fort Rucker, AL 36362

Directorate of Training Development Building 502 Fort Rucker, AL 36362

Chief USAHEL/USAAVNC Field Office P. O. Box 716 Fort Rucker, AL 36362-5349 Commander U.S. Army Aviation Center and Fort Rucker ATTN: ATZQ-CG Fort Rucker, AL 36362

Chief
Test & Evaluation Coordinating Board
Cairns Army Air Field
Fort Rucker, AL 36362

MAJ Terry Newman Canadian Army Liaison Office Building 602 Fort Rucker, AL 36362

German Army Liaison Office Building 602 Fort Rucker, AL 36362

LTC Patrice Cottebrune French Army Liaison Office USAAVNC (Building 602) Fort Rucker, AL 36362-5021

Australian Army Liaison Office Building 602 Fort Rucker, AL 36362

Dr. Garrison Rapmund 6 Burning Tree Court Bethesda, MD 20817

Commandant, Royal Air Force Institute of Aviation Medicine Farnborough Hampshire GU14 6SZ UK

Commander
U.S. Army Biomedical Research
and Development Laboratory
ATTN: SGRD-UBZ-I
Fort Detrick, Frederick, MD 21702

Defense Technical Information Cameron Station, Building 5 Alexandra, VA 22304-6145 Commander, U.S. Army Foreign Science and Technology Center AIFRTA (Davis) 220 7th Street, NE Charlottesville, VA 22901-5396

Director,
Applied Technology Laboratory
USARTL-AVSCOM
ATTN: Library, Building 401
Fort Eustis, VA 23604

Commander, U.S. Air Force
Development Test Center
101 West D Avenue, Suite 117
Eglin Air Force Base, FL 32542-5495

Commander, U.S. Army Missile
Command
Redstone Scientific Information Center
ATTN: AMSMI-RD-CS-R
/ILL Documents
Redstone Arsenal, AL 35898

Dr. H. Dix Christensen Bio-Medical Science Building, Room 753 Post Office Box 26901 Oklahoma City, OK 73190

Director

Army Personnel Research Establishment Farnborough, Hants GU14 6SZ UK

U.S. Army Research and Technology Laboratories (AVSCOM) Propulsion Laboratory MS 302-2 NASA Lewis Research Center Cleveland, OH 44135

Col. Otto Schramm Filho c/o Brazilian Army Commission Office-CEBW 4632 Wisconsin Avenue NW Washington, DC 20016 Dr. Eugene S. Channing 7985 Schooner Court Frederick, MD 21701-3273

LTC Gaylord Lindsey (5)
USAMRDC Liaison at Academy
of Health Sciences
ATTN: HSHA-ZAC-F
Fort Sam Houston, TX 78234

Aviation Medicine Clinic TMC #22, SAAF Fort Bragg, NC 28305

Dr. A. Kornfield, President Biosearch Company 3016 Revere Road Drexel Hill, PA 29026

NVEOD AMSEL-RD-ASID (Attn: Trang Bui) Fort Belvior, VA 22060

CA Av Med HQ DAAC Middle Wallop Stockbridge Hants S020 8DY UK

Commander and Director
USAE Waterways Experiment Station
ATTN: CEWES-IM-MI-R
Alfrieda S. Clark, CD Dept.
3909 Halls Ferry Road
Vicksburg, MS 39180-6199

Mr. Peter Seib Human Engineering Crew Station Box 266 Westland Helicopters Limited Yeovil, Somerset BA202YB UK

Dr. Christine Schlichting Behavioral Sciences Department Box 900, NAVUBASE NLON Groton, CT 06349-5900 COL C. Fred Tyner
U.S. Army Medical Research
& Development Command
SGRD-ZB
Fort Detrick, Frederick, MD 21702-5012

COL John F. Glenn
U.S. Army Medical Research
& Development Command
SGRD-ZC
Fort Detrick, Frederick, MD 21702-5012